

MPE/iX Quick Reference Guide

HP 3000 MPE/iX Computer Systems

Edition 6



32650-90873

E1098

Printed in: U.S.A. October 1998

Notice

The information contained in this document is subject to change without notice.

Hewlett-Packard makes no warranty of any kind with regard to this material, including, but not limited to, the implied warranties of merchantability or fitness for a particular purpose. Hewlett-Packard shall not be liable for errors contained herein or for direct, indirect, special, incidental or consequential damages in connection with the furnishing or use of this material.

Hewlett-Packard assumes no responsibility for the use or reliability of its software on equipment that is not furnished by Hewlett-Packard.

This document contains proprietary information which is protected by copyright. All rights reserved. Reproduction, adaptation, or translation without prior written permission is prohibited, except as allowed under the copyright laws.

Restricted Rights Legend

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013. Rights for non-DOD U.S. Government Departments and Agencies are as set forth in FAR 52.227-19 (c) (1,2).

Hewlett-Packard Company
3000 Hanover Street
Palo Alto, CA 94304 U.S.A.

© Copyright 1994, 1998 by Hewlett-Packard Company

Contents

1. Command Descriptions	
Commands Syntax	10
2. Utilities	
Utilities Descriptions	56
3. Intrinsic Descriptions	
Descriptions of the Intrinsic Available in MPE/iX	70
4. FCOPY Commands	
FCOPY commands	108
5. SORT-MERGE/XL Commands	
Description of SORT-MERGE/XL Commands	114
6. System Debug	
Debugging your system	120
7. File System	
System Defined Files	162
Carriage Control Effect Summary	170
File Access and Security	171
Default Security for Accounts, Groups, and Users	172
Net Default Access to Files	173
Capability List	174
Default Capabilities	175
FOPEN FOPTIONS	176
FOPEN AOPTIONS	177
8. ASCII Character Set	
ASCII Character Set	180

Tables

Table 7-1. FFILEINFO File codes	163
Table 7-2. Carriage Control Directives	167
Table 7-3. File Access and Security	171
Table 7-4. Security for Accounts, Groups and Users.	172
Table 7-5. Net Default Access to Files	173
Table 7-6. Capability List	174
Table 7-7. Default Capabilities	175
Table 8-1. ASCII Character Set	180

Preface

MPE/iX, Multiprogramming Executive with Integrated POSIX, is the latest in a series of forward-compatible operating systems for the HP 3000 line of computers.

In HP documentation and in talking with HP 3000 users, you will encounter references to MPE XL, the direct predecessor of MPE/iX. MPE/iX is a superset of MPE XL. All programs written for MPE XL will run without change under MPE/iX. You can continue to use MPE XL system documentation, although it may not refer to features added to the operating system to support POSIX (for example, hierarchical directories).

Finally, you may encounter references to MPE V, which is the operating system for HP 3000s, not based on the PA-RISC architecture. MPE V software can be run on the PA-RISC (Series 900) HP 3000s in what is known as *compatibility mode*.

The MPE/iX Quick Reference Guide offers a synopsis of the MPE/iX operating system and its major subsystems. Each chapter corresponds to a manual in the MPE/iX set. The table below lists the chapters in order and the corresponding MPE/iX manuals.

Chapter	Manual
Commands	<i>MPE/iX Commands Reference Manual Volumes 1 and 2)</i>
Utilities	<i>MPE/iX Utilities Manual</i>
Intrinsics	<i>MPE/iX Intrinsics Reference Manual</i>
FCOPY	<i>FCOPY Reference Manual</i>
SORT-MERGE	<i>SORT-MERGE/XL General User's Guide</i>
System Debug	<i>MPE/iX System Debug Reference Manual</i>
File System	<i>Using the 900 Series HP 3000: Fundamental Skills</i> <i>Using the 900 Series HP 3000: Advanced Skills</i>

Commands, intrinsics, and utility descriptions are in alphabetical order within the chapters. Each of the chapters shows syntax for commands and functions. Some chapters include examples; user input is underlined.

Use the Table of Contents to look up information within the sections.

1 Command Descriptions

Commands Syntax

These are abbreviated descriptions for the commands for MPE/iX.

ABORT

Aborts the current program or operation.

```
ABORT  
ABORT
```

ABORTIO/ =ABORTIO

Aborts one pending I/O request for a device.

```
ABORTIO ldev  
  
=ABORTIO ldev  
  
ABORTIO 53  
ABORTIO 53
```

ABORTJOB/ =ABORTJOB

Aborts a job or session.

```
ABORT JOB { #Jnnn  
            #Snnn  
            [jobname, ] user.acct }  
  
=ABORTJOB { #Jnnn  
            #Snnn  
            [jobname, ] user.acct }  
  
ABORTJOB #S139
```

ACCEPT

Permits a designated device to accept jobs/sessions and/or data.

```
ACCEPT [ JOBS  
         DATA ] ,ldev  
  
ACCEPT 19
```

ALLOCATE

Loads a compatibility mode program or procedure into virtual memory.

```
ALLOCATE [ PROCEDURE,  
           PROGRAM,   ] name  
  
ALLOCATE PROCEDURE, PROC1
```

ALLOW

Grants a user access to a specific operator command.

```
ALLOW FILE= formaldesignator[ ;SHOW]
```

OR

```
ALLOW { @.@
        user.@
        @.acct
        user.acct } ;COMMANDS=command[ ,command, ...]

ALLOW FILE=ALLOWTMP;SHOW
ALLOW USER.TECH;COMMANDS=REPLY,ABORTIO
```

OR

```
ALLOW
>MGR.MANUAL;COMMANDS=BREAKJOB
>EXIT
```

ALTACCT

Changes the attributes of an existing account. See Chapter 7 for a listing of account capabilities and defaults.

```
ALTACCT acctname

[ ;PASS=[password] ][ ;FILES=[filespace] ][ ;CPU=[cpu] ]
[ ;CONNECT=[connect] ]

[ ;CAP=[capabilitylist] ][ ;ACCESS=[fileaccess] ]
[ ;MAXPRI=[subqueue] ]

[ ;LOCATTR=[localattribute] ][ ;ONVS=volumesetname ]
ALTACCT AC2;PASS=GLOBALX;FILES=50000
```

ALTGROUP

Changes one or more attributes of a group.

```
ALTGROUP groupname[ .acctname] [ ;PASS=[password] ]
[ ;CAP=[capabilitylist] ]

[ ;FILES=[filespace sectors] ] [ ;CPU=[cpu seconds] ]
[ ;CONNECT=[connect minutes] ]

[ ;ACCESS=[fileaccess] ] [ ;ONVS=volumesetname ]
[ ;HOMEVS=volumesetname ]

ALTGROUP GROUPX;PASS=PASS2

ALTGROUP LEILA;ONVS=TIME_LORD;FILES=10000
ALTGROUP LEILA;HOMEVS=DICHONDRITE
```

ALTJOB

Alters the attributes of waiting or scheduled jobs.

```
ALTJOB [JOB=] {#Jnnn
              #Snnn} [ ;INPRI=inputpriority]

[ ;OUTDEV={ldev
           devclass} ][ ;JOBQ=jobqueue] [ ;HIPRI ]
ALTJOB #J1;INPRI=10;OUTDEV=LP
```

ALTLOG

Alters the attributes of an existing user logging identifier.

Commands Syntax

```
ALTLOG logid [ ;LOG=logfile { ,DISC
                ,TAPE } ] [ ;PASS=password ]
[ { ;AUTO
  ;NOAUTO } ]
ALTLOG KIM;LOG=C,DISC
```

ALTPROC

Changes the priority for the specified process(es) *if* you have OP or SM capability. **Native Mode**

```
ALTPROC [ [ ;PIN=] { pinspec } ]
        { ( pinspec [ , pinspec ] ... ) }
[ [ ;JOB=] { jobspec } ]
        { ( jobspec [ , jobspec ] ... ) }
{ [ ;PRI=] pri
  [ ;WG=] { workgrp
          NATURAL_wg } }
[ ;TREE | ;NOTREE ]
[ ;USER | ;ANYUSER ]
[ ;SYSTEM ]

ALTPROC 42;PRI=CM
ALTPROC 0;PRI=DS
ALTPROC job=mgr.payroll; PRI=155
ALTPROC #p133;TREE;PRI=CS
ALTPROC (150,#p247,211);PRI=ES
ALTPROC job=@j; PRI=CS;ANYUSER
ALTPROC job=@j;PRI=CS; USER
```

ALTSEC

Changes the access permissions by altering the access control definition (ACD). Access permissions may be changed for a

- file
- hierarchical directory
- device
- device class

File access masks can also be changed with this command (only files have access masks). The file status change time stamp is updated by ALTSEC.

NOTE The ALTSEC command does not change access permissions for MPE groups, accounts, or the root directory.

Syntax

```
ALTSEC objectname [ , { FILENAME
                    LDEV
                    DEVCLASS } ]
[ ; [ACCESS=] (fileaccess [ ; [fileaccess] [ ; ... ] ] ) ]
[ { ;NEWACD=
  ;REPACD=
  ;ADDPAIR=
  ;REPPAIR= } { ( acdpair [ ; acdpair] [ ; ... ] )
                ^filereference } ]
[ ;DELPAIR= { ( userspec [ ; userspec] [ ; ... ] )
              ^filereference } ]
[ ;COPYACD= objectname { , FILENAME
                        , LDEV } ] [ ;DELACD ] [ ;MASK ]
```

ALTSPOOLFILE

Alters the characteristics of an output spoolfile.

```
ALTSPOOLFILE {#Onnm
              ldev1} { ;PRI=outputpriority
                    ;COPIES=numcopies
                    ;DEV={ldev2
                          devclass}
                    ;DEFER
              } |;...|
ALTSPOOLFILE #086;DEFER
ALTSPOOLFILE 6;DEFER
ALTSPOOLFILE #0123;PRI=3
```

ALTUSER

Changes the attributes currently defined for a user.

```
ALTUSER username [ .acctname ]
[ ;PASS=[password] ]
[ ;CAP=[capabilitylist] ]
[ ;MAXPRI=[subqueuename] ]
[ ;LOCATTR=[localattribute] ]
[ ;HOME=[homegroupname] ]
[ ;UID=[uid] ]
[ ;USERPASS={REQ [ , EXPIRED] }
             {OPT} ]

ALTUSER JONES ;CAP=IA,BA,SF,PH,DS,MR
ALTUSER JONES ;PASS=JJ ;MAXPRI=DS
```

ASSOCIATE

Gives a user operator control of a device class.

```
ASSOCIATE devclass
ASSOCIATE TAPE
```

BASIC

Interprets a compatibility mode BASIC/V program.

```
BASIC [commandfile] [ , [inputfile] [ , listfile] ]
BASIC MYCOMDS ,MYDATA ,MYLIST
```

BASICGO

Compiles, prepares, and executes a compatibility mode BASIC/V program.

```
BASICGO [commandfile] [ , listfile ]
BASICGO
$CONTROL USLINIT
$COMPILE MYPROG
$EXIT
```

BASICOMP

Compiles a compatibility mode BASIC/V program.

```
BASICOMP [commandfile] [ , [usfile] [ , listfile] ]
BUILD OBJECT ;CODE=USL
BASICOMP , OBJECT
$CONTROL USLINIT
$COMPILE MYPROG
$EXIT
```

BASICPREP

Compiles and prepares a compatibility mode BASIC/V program.

```
BASICPREP [commandfile][, [progfile][, listfile]]  
BASICPREP,MYCOMDS
```

BBASIC

Starts execution of the HP Business BASIC/V interpreter in compatibility mode.

```
BBASIC [commandfile][, [inputfile][, listfile]]  
BBASIC
```

BBASICGO

Compiles, prepares, and executes an HP Business BASIC/V program in compatibility mode.

```
BBASICGO infile[, listfile]  
BBASICGO MYPROG,LISTFL
```

BBASICOMP

Compiles an HP Business BASIC/V program in compatibility mode.

```
BBASICOMP infile[, [ustfile][, listfile]]  
BBASICOMP MYPROG,OBJECT
```

BBASICPREP

Compiles and prepares a HP Business BASIC/V program in compatibility mode.

```
BBASICPREP infile[, [progfile][, listfile] ]  
BBASICPREP MYCOMDS,MYPROG
```

BBXL

Initiates execution of the HP Business BASIC/XL interpreter.

```
BBXL [commandfile][, [inputfile][, [listfile]]] [;XL=xllist]  
BBXL
```

BBXLCOMP

Compiles an HP Business BASIC/XL program.

```
BBXLCOMP textfile[, [objectfile][, listfile]]  
BBXLCOMP MYPROG,OBJECT
```

BBXLGO

Compiles, links, and executes an HP Business BASIC/XL program.

```
BBXLGO textfile[, [listfile]] [;XL=xllist]  
BBXLGO MYPROG,LISTFL
```

BBXLLK

Compiles and links an HP Business BASIC/XL program.

```
BBXLLK textfile [ , [progfile] [ , [listfile] ] ]
BBXLLK MYSCR,MYPROG
```

BREAKJOB

Suspends an executing job.

```
BREAKJOB #Jmn
BREAKJOB #J68
```

BUILD

Creates and immediately allocates a new empty file on disk.

```
BUILD filereference
[ ;REC=[ [resize] [ , [blockfactor] [ , [F
                                U
                                V
                                B] [ ,BINARY
                                ,ASCII ] ] ] ] ]
[ ;CCTL
  ;NOCCTL] [ ;TEMP] [ ;DEV= [ dsdevice#
                             dsdevice#device
                             device ] ]
[ ;CODE=filecode] [ ;DISC=[ [numrec] [ , [numextents] [ , [initialloc] ] ] ]
[ ;RIO
  ;NORIO] [ ;MSG
           ;CIR
           ;STD
           ;KSAMXL
           ;SPOOL] [ ;ULABEL=numlabels] [ ;KEY={ ^filereference
                                                    keyinfo } ]
[ ;FIRSTREC=recnum] [ ;REUSE
                     ;NOREUSE]
```

Where:

```
;KEY= ( keytype,keylocation,keysize [ , DUP
                                             ,RDUP ] );
.
.
.
keytype,keylocation,keysize [ , DUP
                              ,RDUP ] )
BUILD WORKFILE;REC=-80,3,F,ASCII;DISC=2000,10,2
BUILD VFILE;DISC=500,10,1;REC=-80;DEV=VCLASS1
BUILD NEWDATA;DISC=3000,1,1;CODE=LOG
```

BYE

Ends an interactive session.

```
BYE
BYE
```

CALC

Evaluates an expression.

```
CALC expression
CALC 5*10-7
```

CCXL

Compiles an HP C/iX program.

```
CCXL [ textfile ] [ , [ objectfile ] ] [ , [ listfile ] ] [ ; INFO=quotedstring ]
CCXL
```

CCXLGO

Compiles, links, and executes an HP C/iX program.

```
CCXLGO [ textfile ] [ , [ listfile ] ] [ ; INFO=quotedstring ]
CCXLGO SOURCE,LISTFILE
```

CCXLLK

Compiles and links an HP C/iX program.

```
CCXLLK [ textfile ] [ , [ [ progfile ] ] [ , [ listfile ] ] ] [ ; INFO=quotedstring ]
CCXLLK SOURCE,PROG
```

CHANGELOG

Changes the user logging file without stopping or interrupting the logging process.

```
CHANGELOG logid [ ; DEV=device ]
CHANGELOG KATHY
```

CHDIR

Changes the process' current working directory (CWD).

Syntax

```
CHDIR [ [ DIR=dir_name ] [ ; SHOW | NOSHOW ]
CHDIR /MYACCT/MYGRP/dir1 |
```

CHGROUP

Switches you from the current group to any other group within the logon account to which you are allowed access.

```
CHGROUP [ [ groupname ] [ /grouppass ] ]
CHGROUP GORODA
```

COB74XL

Compiles an HP COBOL II/XL program using the 1974 ANSI standard entry point and creates an object file.

```
COB74XL [ textfile ] [ , [ objectfile ] ] [ , [ listfile ] ] [ , [ masterfile ] ] [ , [ newfile ] ] ] ]
[ ; INFO=quotedstring ] [ ; WKSP=workspacename ] [ ; XDB=xdbfilename ]
COB74XL SOURCE,OBJECT,LISTFL
```

COB74XLG

Compiles, links, and executes an HP COBOL II/XL program using the ANSI 1974 standard entry point.

```
COB74XLG [textfile][,[listfile][,[masterfile][,newfile]]]
[;INFO=quotedstring][;WKSP=workspacename][;XDB=xdbfilename]
COB74XLG TEXTFL,LISTFL
```

COB74XLK

Compiles and links an HP COBOL II/XL program using the 1974 ANSI standard entry point.

```
COB74XLK [textfile][,[progfile][,[listfile][,[masterfile][,newfile]]]]
[;INFO=quotedstring][;WKSP=workspacename][;XDB=xdbfilename]
COB74XLK SFILE,MYPROG
```

COB85XL

Compiles an HP COBOL II/XL program using the 1985 ANSI standard entry point and creates an object file.

```
COB85XL [textfile][,[objectfile][,[listfile][,[masterfile][,newfile]]]]
[;INFO=quotedstring][;WKSP=workspacename][;XDB=xdbfilename]
COB85XL SOURCE,OBJECT,LISTFL
```

COB85XLG

Compiles, links, and executes an HP COBOL II/XL program using the ANSI 1985 standard entry point.

```
COB85XLG [textfile][,[listfile][,[masterfile]
[ ,newfile]]]
[;INFO=quotedstring][;WKSP=workspacename][;XDB=xdbfilename]
COB85XLG TEXTFL,LISTFL
```

COB85XLK

Compiles and links an HP COBOL II/XL program using the 1985 ANSI standard entry point.

```
COB85XLK [textfile][,[progfile][,[listfile][,[masterfile][,newfile]]]]
[;INFO=quotedstring][;WKSP=workspacename][;XDB=xdbfilename]
COB85XLK SFILE,MYPROG
```

COBOLII

Compiles a compatibility mode COBOLII program on the COBOL 74 compiler.

```
COBOLII [textfile][,[uslfile][,[listfile][,[masterfile][,newfile]]]]
[;INFO=quotedstring][;WKSP=workspacename]
BUILD OBJECT;CODE=USL
COBOLII SOURCE,OBJECT,LISTFL
```

COBOLIIGO

Compiles, prepares, and executes a compatibility mode COBOLII program on the COBOL 74 compiler.

```
COBOLIIGO [textfile][,[listfile][,[masterfile][,newfile]]]
[;INFO=quotedstring][;WKSP=workspacename]
COBOLIIGO TEXTFL,LISTFL
```


DATA

Enters data into the system from a device file. (Cannot be used to enter data from \$STDIN.)

```
DATA[jsname , ]username [ /userpass ] . acctname [ /acctp ] [ ;filename ]
DATA SESSB , BROWN . ACCT1
.
.
: EOD
```

DEALLOCATE

Deallocates a program or procedure previously loaded into memory with the ALLOCATE command.

```
DEALLOCATE [ PROGRAM
            PROCEDURE ], name
DEALLOCATE PROGEX
```

DEBUG

Instructs MPE/iX to enter the system debugger.

```
DEBUG [ commands ]
DEBUG TRACE ; C
```

DELETESPOOLFILE

Deletes a spoolfile from disk.

```
DELETESPOOLFILE { #Onnn
                  #Innn
                  ldev }
DELETESPOOLFILE 6
```

DELETEVAR

Deletes one or more MPE/iX session variables.

```
DELETEVAR varname [ , varname ] . . . [ , varname ]
DELETEVAR firstvariable , secondvariable
DELETEVAR JOBNUM , SESSNUM
```

DISALLOW

Prohibits access to a specific operator command.

```
DISALLOW FILE=formaldesignator [ ; SHOW ]
DISALLOW { @ . @
          user . @
          @ . acct
          user:acct } ; COMMANDS=command [ , command , . . . ]
DISALLOW USER . TECH ; COMMANDS=REPLY , ABORTIO
```

DISASSOCIATE

Removes control of a device class from the user.

```
DISASSOCIATE devclass
DISASSOCIATE TAPE
```

DISCRPS

Enables or disables the rotational position sensing (RPS) feature on a specified logical device.

```
DISCRPS ldev { ,ENABLE [ { ,value,value } ]  
              ,DISABLE }  
DISCRPS 1,ENABLE
```

DISKUSE

Displays disk space usage, in sectors, for one or more directories or a directory tree.

Syntax

```
DISKUSE [ [DIR=dir_name] [ ; TREE | NOTREE | USERNAME ]  
DISKUSE mydir.group.acct
```

DISMOUNT

Causes a volume set that was explicitly reserved by the user (with a MOUNT or VSRESERVE command) to be released. The equivalent MPE/iX command is VSRELEASE.

```
DISMOUNT [ { *  
           (blank)  
           volumesetname } ] [ .groupname [ .acctname ] ]  
DISMOUNT MYSET.B.C
```

DO

Allows the user to reexecute any command still retained in the command line history stack.

```
DO [CMD=cmdid] [ ; EDIT=editstring ]  
DO 10
```

DOWN

Removes a device from normal system use. This command does not apply to disks.

```
DOWN ldev  
DOWN 7
```

DOWNLOAD

Downloads format information to a line printer.

```
DOWNLOAD ldev [ ,filename  
              ,MARGIN=nm ] [ , ... ]  
DOWNLOAD 11,VFCPAY
```

DSTAT

Displays the current status of the disk drives on the system.

```
DSTAT [ ldev  
       ALL ]  
DSTAT ALL
```

ECHO

Displays a message on the standard list device.

```
ECHO [message]
SETVAR a, 'hi there'
ECHO !a, Cathy
```

EDITOR

Starts the EDIT/3000 subsystem.

```
EDITOR [listfile]
FILE LISTFILE;DEV=LP
EDITOR *LISTFILE
```

ELSE

Provides an alternate execution sequence for an IF statement in a jobfile or user command within an IF statement.

```
ELSE
!CONTINUE
!PASXL MYPROG,MYUSL
!IF JCW>=FATAL THEN
!  TELL USER.TECHPUBS;COMPILE FAILED
!ELSEIF JCW ≥ WARN THEN
!  TELL USER.TECHPUBS;COMPILE COMPLETED WITH WARNINGS
!ELSE
!  TELL USER.TECHPUBS;COMPILE COMPLETED WITH NO WARNINGS
!ENDIF
```

ELSEIF

Provides an alternate execution sequence for an IF statement.

```
ELSEIF expression [THEN]
IF EXPN1 THEN
...
ELSEIF EXPN2 THEN
...
ELSEIF EXPN3
...
ELSE
...
ENDIF
```

ENDIF

Terminates an IF block.

```
ENDIF

IF
.
.
.
ENDIF
```

ENDWHILE

Terminates a WHILE block.

Commands Syntax

```

ENDWHILE
WHILE logical_expression
.
.
ENDWHILE

```

EOD

Denotes end-of-data on input stream from a jobfile (from an input other than \$STDIN). It also terminates data initialized by the DATA command. The colon (:) is a required part of this command.

```

: EOD
DATA SESS1, BLACK.ACCTSP
... data ...
: EOD

```

EOJ

Ends a batch job.

```

EOJ

!JOB USER.PUBS
!RUN MYPROG1
!RUN MYPROG2
!EOJ

```

ERRCLEAR

Zeros out all HP predefined error-related variables.

```

ERRCLEAR

ERRCLEAR

```

ERRDUMP

Allows a user to dump either the process or system error stack to a specified depth.

```

ERRDUMP [errorstackdepth][;SYS]

ERRDUMP 1;SYS

```

ESCAPE

Allows the CI programmer to simulate all aspects of CI error handling. Control leaves all user commands and returns to the CI (unless a CONTINUE is in effect).

```

ESCAPE [ [CIERR=] errnum ]

cmd1
CONTINUE
udc1
           ucmdA
           ucmdB
           ESCAPE
cmd2

```

EXIT

Terminates the command interpreter.

```
EXIT
EXIT
```

FCOPY

Runs the FCOPY subsystem.

```
FCOPY [fcopycommand]
FCOPY FROM=UDC.TECHPUBS;TO=TEMP;NEW
```

FILE

Declares the file attributes to be used when a file is opened. This declaration, informally known as a file equation, may be used to override programmatic or system default file specifications. With the addition of shared parameters from the NS3000/XL AdvanceNet subsystem, the declaration may specify a formal file designator that may be used to access a remote file or device in a subsequent command or intrinsic. NS3000/XL AdvanceNet is not part of the 900 Series HP 3000 Computer System Fundamental Operating System and must be purchased separately.

```
FILE formaldesignator =[*formaldesignator
    $NULL
    $NEWPASS
    $OLDPASS
    $STDIN
    $STDINX
    $STDLIST
    filereference]
[ :nodespec
  ,filedomain] [ ;DEV=[ [envname]#][device][ , [ outpri ] [ , numcopies ] ] ]
[ ;VTERM ] [ ;ENV=envfile [ :nodespec ] ] [ ;option ] [ ;access ] [ ;DEL
    ;TEMP
    ;SAVE
    ;SPSAVE ]
```

Syntax for Option:

```
[ ;REC=[recsize][ , [ blockfactor ] ] [ , [ F
    U
    V ] ]
    B [ , BINARY
    , ASCII ] ] ]
[ ;DEN=[density ] ] [ ;DISC=[numrec][ , [ numextents ] [ , initialloc ] ] ]
[ ;CODE=filecode ]
[ ;RIO
  ;NORIO ] [ ;STD
    ;MSG
    ;CIR
    ;KSAMXL
    ;SPOOL ] [ ;ULABEL=numlabels ]
[ ;KEY={^filereference
  keyinfo } ] [ ;FIRSTREC=recnum ] [ ;REUSE
    ;NOREUSE ]
```

Syntax for *keyinfo*:

```
;KEY=(keytype,keylocation,keysize [ , DUP
    , RDUP ] ; [ vellip ] keytype,keylocation,keysize
[ , DUP
  , RDUP ] )
```

Syntax for Access:

```

[ ;NOCCTL [ ;NOMULTI [ ;NOMR [ ;WAIT [ ;ACC= [ IN
;CCTL] ;MULTI ;MR ] ;NOWAIT] OUT
;GMULTI] UPDATE
OUTKEEP
APPEND
INOUT] ]

[ ;BUF=[numbuffers] [ ;LOCK [ ;COPY ;NOLOCK ] ;NOCOPY ] [ ;FORMS=formsmg]
;NOBUF]

[ ;EXC
;SHR
;EAR
;SEMI ]

[ ;NOLABEL
;LABEL=[ [valid][ , [ IBM
ANS][ , [expdate][ , [seq ] ] ] ] [ ;FORMID=formid]
[ ;PRIVATE]

FILE SOURCE=INX
FILE DEST=OUTX
RUN MYPROG
FILE DEST=FILEX,NEW;REC=64,2,F,ASCII;DISC=800,10,2;SAVE
RUN MYPROG
FILE SOURCE=TAPE1,OLD;DEV=TAPE;REC=-80
FTNXL *SOURCE
FILE FTNTEXT=*SOURCE
FILE X= ./my_file;SAVE
PURGE *X

```

FINDDIR (UDC)

The FINDDIR UDC executes the LISTFILE command to search for a directory.

NOTE System-defined UDCs are not automatically available. Your System Manager must use the SETCATALOG command to make these UDCs available for your use. For example:

```
SETCATALOG HPPXUDC.PUB.SYS
```

Syntax

```
FINDDIR [ [DIR=]dir_name][ [START=]start_dir]
```

Refer to the LISTFILE command later in this chapter for examples.

FINDFILE (UDC)

The FINDFILE UDC executes the LISTFILE command to search for a file.

NOTE System-defined UDCs are not automatically available. Your System Manager must use the SETCATALOG command to make these UDCs available for your use. For example:

```
SETCATALOG HPPXUDC.PUB.SYS
```

Syntax

```
FINDFILE [FILE=]filename[ [START=]start_dir]
```

FORMSALIGN

Configures one spooled printer or a group of spooled printers related by device class, to conditionally enter into a forms message dialog with its operator when the current spoolfile includes a forms message.

```
FORMSALIGN [ DEV= ] { ldev
                      devclass
                      devname }
[ ;DIALOG= ] { { EACHCHANGE
               EACHFILE
               EACHCOPY } [, { FORMIDOVERRIDE
                               NOFORMIDOVERRIDE } ] } ]
[ ;SHOW ]
FORMSALIGN LP;SHOW
```

FORTGO

Compiles, prepares, and executes a compatibility mode FORTRAN 66/V program.

```
FORTGO [textfile][ , [listfile][ , [masterfile][ , [newfile] ] ] ]
[ ;INFO=quotedstring ]
FORTGO SOURCE,LISTFL
```

FORTPREP

Compiles and prepares a compatibility mode FORTRAN 66/V program.

```
FORTPREP [textfile][ , [progfile][ , [listfile][ , [masterfile][ , [newfile] ] ] ] ]
[ ;INFO=quotedstring ]
FORTPREP TEXTX,PROGX,LISTX
```

FORTRAN

Compiles a compatibility mode FORTRAN 66/V program.

```
FORTRAN [textfile][ , [usfile][ , [listfile][ , [masterfile][ , [newfile] ] ] ] ]
[ ;INFO=quotedstring ]
FORTRAN MYSOURCE,MYUSL,MYLIST;INFO= "$CONTROL BOUNDS"
```

FREERIN

Releases a global resource identification number (RIN).

```
FREERIN rin
FREERIN 1
```

FTN

Compiles a compatibility mode FORTRAN 77/V program.

```
FTN [textfile][ , [ustfile][ , [listfile] ] ] [ ;INFO=quotedstring ]
BUILD FORTOBJ;CODE=USL
FTN FORTSRC,FORTOBJ,LISTFILE
```

FTNGO

Compiles, prepares, and executes a compatibility mode HP FORTRAN 77/V program.

```
FTNGO [textfile][, listfile][; INFO=quotedstring]  
FTNGO FORTSRC,LISTFILE
```

FTNPREP

Compiles and prepares a compatibility mode HP FORTRAN 77/V program.

```
FTNPREP [textfile], [progfile][, listfile][; INFO=quotedstring]  
FTNPREP FORTSRC,FORTPROG
```

FTNXL

Compiles an HP FORTRAN 77/iX program.

```
FTNXL [textfile][, [objectfile][, [listfile]]][; INFO=quotedstring]  
FTNXL FORTSRC,FORTOBJ,LISTFILE
```

FTNXLGO

Compiles, links, and executes an HP FORTRAN 77/iX program.

```
FTNXLGO [textfile][, [listfile]]][; INFO=quotedstring]  
FTNXLGO FORTSRC,LISTFILE
```

FTNXLK

Compiles and links an HP FORTRAN 77/iX program.

```
FTNXLK [textfile][, [progfile][, [listfile]]][; INFO=quotedstring]  
FTNXLK FORTSRC,FORTPROG
```

GETLOG

Establishes a logging identifier on the system.

```
GETLOG logid;LOG=logfile [,DISC  
                                ,TAPE] [;PASS=password][;AUTO  
                                ;NOAUTO]  
GETLOG FINANCE;LOG=A,DISC
```

GETRIN

Acquires a global resource identification number (RIN) and assigns a password to it.

```
GETRIN rinpassword  
GETRIN MYRIN
```

HEADOFF

Stops header/trailer output to a device.

```
HEADOFF ldev  
HEADOFF 6
```

HEADON

Resumes header/trailer output to a device.

```
HEADON ldev
HEADON 6
```

HELLO

Initiates an interactive session.

```
HELLO [session , ]user [ /userpass ] .acct [ /acctpass ] [ ,group [ /grouppass ] ]
[ ;TERM={termtype
      termname } ] [ ;TIME=cpusecs ] [ ;PRI={BS
                                                    CS
                                                    DS
                                                    ES} ]
[ ;INPRI=inputpriority
  ;HIPRI][ ;INFO=ciinfo ] [ ;PARM=ciparm ]
HELLO USER.TECHPUBS
```

HELP

Accesses the HELP subsystem.

Direct access:

```
HELP [ {udcfilename
      commandname [ keyword ] [ ,ALL ]
      commandfilename
      programfilename
      SUMMARY
      CLASS
      HELPSTUDY
      FUNCTIONS
      EXPRESSIONS
      VARIABLES
      OPERATORS } ]
```

Interactive (subsystem) access:

```
commandname {space or comma} keyword [ ,ALL ]

HELPMENU
SUMMARY
CLASS
HELP
HELPSTUDY

HELP ABORT
HELP LINKALL.TEST.UI
```

IF

Used to control the execution sequence of a job, UDC, or command file.

```
IF expression [ THEN ]
!PASXL MYPROG,MYUSL
!IF JCW>=FATAL THEN
! TELL USER.TECHPUBS;COMPILE FAILED
!ELSE
! TELL USER.TECHPUBS;COMPILE COMPLETED
!ENDIF
```

INPUT

Permits the user to assign a string to any variable. All numeric input is treated as a string. See `TYPEOF` function in appendix B of the *MPE/iX Commands Reference Manual*, and `SETVAR` command in the same manual.

```
INPUT [NAME=]varname [ ; PROMPT=prompt ] [ ; WAIT=seconds ] [ READCNT=chars ]
INPUT Response; "Enter YES or NO>"
INPUT Response; "Press any key to continue"
```

JOB

Defines a job to be activated with the `STREAM` command to run in batch mode.

```
JOB [jobname, ]username [ /userpass ] .acctname [ /acctpass ]
[ , groupname [ /grouppass ] ]
[ ; TIME=cpusecs ] [ ; PRI={BS
                        CS
                        DS
                        ES} ]
[ ; INPRI=inputpriority
  ; HIPRI ]
[ ; RESTART ] [ ; OUTCLASS=[ [ device ] [ , [ outputpriority ] [ , numcopies ] ] ] ]
[ ; TERM={termtype} ] [ ; PRIVATE ] [ ; SPSAVE ] [ JOBQ=queue name ]
RUN EDITOR.PUB.SYS
/ADD
    1 !JOB WXYZ,WRITER.TEC
    2 !EDITOR
    3 TEXT ABC
    4 LIST ALL,OFFLINE
    5 EXIT
    6 !EOJ
    //
/KEEP MYJOB
/EXIT
:
STREAM MYJOB
STREAM
JOB USER.TECHPUBS;OUTCLASS=12
```

JOBFENCE

Defines the minimum input priority that a job or session must have in order to execute.

```
JOBFENCE priorityfence
JOBFENCE 8
```

JOBPRI

Sets or changes the default execution priority for batch jobs and sets a maximum execution priority for batch jobs.

```
JOBPRI [maxsubqueue] [ , defaultsubqueue ]
JOBPRI 0
```

JOBSECURITY

Designates what level of user may request resources and control the execution of jobs.

```
JOBSECURITY {HIGH
             LOW }
[ ; PASSEXEMPT={none} {user} , {xaccess} , {max} ]
JOBSECURITY LOW
```

LDISMOUNT

Negates a previously issued LMount or VSRESERVE command. This informs the system that the volume set is no longer reserved system-wide. The equivalent native mode command is VSRELEASESYS.

```
LDISMOUNT [ *
            volumesetname ][ , groupname [ .acctname ] ]
LDISMOUNT DATABASE.PAYROLL.ACCTNG
```

LIMIT

Limits the number of concurrently running jobs/sessions.

```
LIMIT [[+ | -] numberjobs]
      [[+ | -], numbersessions ] [ ;JOBQ=qname ]

LIMIT 2,15
```

LINK

Creates an executable program file by merging the relocatable object modules from all the files in its FROM= parameter.

```
LINK [FROM=file[ ,file[ ,... ] ] [ ;TO=destfile ]
     [ ;RL=rfile[ ,rfile[ ,... ] ] [ ;XL=xfile[ ,xfile[ ,... ] ] ]
     [ ;CAP=caplist ] [ ;NMSTACK=nmstacksize ] [ ;NMHEAP=nmheapsize ]
     [ ;UNSAT=unsatname ]
     [ ;PARMCHECK=checklevel ] [ ;ENTRY=entryname ] [ ;NODEBUG ] [ ;MAP ]
     [ ;SHOW ]
LINK FROM=OBJCODE ;TO=EXECPROG ;NMSTACK=50000 ;MAP ;SHOW
```

LISTACCT

Displays information about one or more accounts.

Syntax

```
LISTACCT [ acctset ] [ , listfile ] [ ;PASS ]
         [ ;FORMAT={SUMMARY|BRIEF|DETAIL} ]
LISTACCT HPXLII ;PASS
```

LISTDIR (UDC)

The LISTDIR UDC executes the LISTFILE command to list all files that are directories.

NOTE System-defined UDCs are not automatically available. Your System Manager must use the SETCATALOG command to make these UDCs available for your use. For example,

```
SETCATALOG HPPXUDC.PUB.SYS
```

Syntax

```
LISTDIR [ [DIR=]dir_name ] [ [FORMAT=]format_opt ]
```

LISTEQ

Displays all active file equations for a job or session.

```
LISTEQ [listfile]  
  
LISTEQ  
  
FILE EQUATIONS  
  
FILE TAPE1;DEV=ATAPE  
FILE PP;ENV=LP2.ENV.OSE;DEV=EPOC  
FILE MYFILE,NEW;REC=-80,3,F,ASCII;DISC=5000;SAVE  
FILE POSIX=./mydir/myfile1
```

LISTF

Displays information about one or more permanent files.

```
LISTF [fileset][,listlevel][;listfile]  
LISTF
```

LISTFILE

Lists file information.

```
LISTFILE [{fileset ((fileset [,fileset ]))}] [ [;FORMAT=] format_opt ]  
[ [;SELEQ=] select_eq ]  
[ [;NAME=] pattern ]  
[;PASS][;PERM  
    ;TEMP  
    ;PERMTEMP]  
[ ;USERNAME  
    ;TREE  
    ;NOTREE ]
```

Selection equations, *enclosed in square brackets*, have the following format:

```
[FTYPE = KSAMXL | SPOOL] [OBJECT = ACCT | GROUP | FILE | DIR]  
[ACCESS = INUSE | OPEN | LOCKED | EXCLUSIVE]  
[CODE = filecodenumber | PRIV | filecode mnemonic]
```

NOTE Selection equations must be surrounded by square brackets.

```
LISTFILE KSAMFMT, 7  
LISTFILE ,DISC  
LISTFILE [a-f]#[g-z@],3;SELEQ=[FTYPE=SPOOL]
```

LISTFTEMP

Displays information about one or more temporary files.

```
LISTFTEMP [fileset][,listlevel][;listfile]  
  
LISTFTEMP
```

LISTGROUP

Displays information for one or more groups.

```
LISTGROUP [ groupset ] [ , listfile ] [ ; PASS ] [ ; FORMAT={ SUMMARY | BRIEF | } ]
LISTGROUP DEVELOP ; PASS ; FORMAT=SUMMARY
LISTGROUP @. @ ; FORMAT=BRIEF
```

LISJOBQ

Displays all job queues on system.

LISTLOG

Lists currently active logging identifiers on the system and whether automatic log file changing has been enabled.

```
LISTLOG [ logid [ ; PASS ] ]
LISTLOG
```

LISTREDO

Displays the contents of the command line history stack. You may specify the format in which the listing will appear, and whether it will appear on \$STDLIST or in a file.

```
LISTREDO [ START=m ] [ ; END=n ] [ ; OUT=outfile ] [ ; ABS
; REL
; UNN ]
LISTREDO -10 , -2 ; OUT=*LIST ; UNN
```

LISTSPF

```
LISTSPF [ [ IDNAME= ] { spoolid
( spoolid [ , spoolid ] . . . ) } ]
[ [ ; SELEQ= ] { select-eq
^indirect_file } ] [ ; DETAIL
; STATUS ]
```

Where the select equation, *enclosed in square brackets*, has the following format:

```
select-eq :: = [ equation ]
equation :: = { parm { >
>=
<
<= <>
=} value
NOT ( equation )
( equation ) { AND
OR } ( equation ) }
LISTSPF O@ ; SELEQ=[ ( PRI > 2 ) AND ( DATE < 09 / 30 / 89 ) ] ; DETAIL
```

LISTUSER

Displays information for one or more users.

```
LISTUSER [ userset ] [ , listfile ] [ ; PASS ]
[ ; FORMAT={ SUMMARY | BRIEF | DETAIL } ]
LISTUSER PETE ; PASS
LISTUSER PETE ; PASS ; FORMAT=SUMMARY
LISTUSER @ ; FORMAT=BRIEF
LISTUSER PETE ; FORMAT=DETAIL
```

L MOUNT

Requests a logical reservation of a volume set. This informs the system that the volume set is to be reserved system-wide. The equivalent native mode command is VSRESERVESYS.

```
L MOUNT [ { *
          (blank)
          volumesetname } ] [ .groupname [ .acctname ] ]
[ ; GEN=[genindex] ]
L MOUNT DATABASE.PAYROLL.ACCTNG
VSRESERVESYS DATABASE.PAYROLL.ACCTNG
```

LOG

Starts, restarts, or stops user logging.

```
LOG logid { ,RESTART
            ,START
            ,STOP }
LOG LOGPROCX,START
```

=LOGOFF

Aborts all executing jobs/sessions and prevents any further logon. You may optionally specify one job or one session that is to remain logged on.

```
=LOGOFF [ #Snnn
         #Jnnn ]
CTRL A
=LLOGOFF
```

or

```
CTRL A
=LLOGOFF #S2
```

=LOGON

Enables job/session processing following =LOGOFF.

```
=LOGON
CTRL A
=LLOGON
```

MOUNT

Sends a request to the system to reserve a volume set (keep it online). The set must be on line in order to have the command take effect. The equivalent MPE/iX command is VSRESERVE.

```
MOUNT [ { *
        (blank)
        vsname } ] [ .groupname [ .acctname ] ] [ ; GEN=[genindex] ]
MOUNT MYSET;GEN=43
```

NEWACCT

Creates a new account with an associated account manager and PUB group.

```
NEWACCT acctname ,mgrname [ ; PASS=[password] ] [ ; FILES=[filespace] ]
[ ; CPU=[cpu] ] [ ; CONNECT=[connect] ] [ ; CAP=[capabilitylist] ]
[ ; ACCESS=[fileaccess] ]
```

```
[ ;MAXPRI=[subqueuename]][ ;LOCATTR=[localattribute]]
[ ;ONVS=volumesetname]
NEWACCT ACI,MNGR
NEWACCT DOCTOR,WHO;CAP=IA,BA,GL,AM,AL
NEWACCT DOCTOR,WHO;ONVS=MY_VOL
NEWACCT DOCTOR,WHO;UID=150;GID=120;CAP=IA,BA,SF,ND,GL,AM,AL
```

NEWDIR

Creates a directory.

Syntax

```
NEWDIR [DIR=]dir_name [ ;SHOW | NOSHOW]
NEWDIR /MYACCT/MYGRP/DIR1
NEWDIR dir1.mygroup.myacct
NEWDIR /myacct/jones/cmdf/john
```

NEWLINK

This command creates a link to a file, group, account, or directory.

```
NEWLINK [ LINK=] linkname[ ;TO=] sourceobject[ { ;SYMBOLIC } ]
:NEWLINK LINK=PAYCODE; TO=PAYROLL.CODE.SOFTWARE
:NEWLINK PAYCODE, PAYROLL.CODE.SOFTWARE
```

NEWGROUP

Creates a new group within an account.

```
NEWGROUP groupname [.acctname][ ;PASS=[password]]
[ ;FILES=[filespace]]
[ ;CPU=[cpu]][ ;CONNECT=[connect]][ ;CAP=[capabilitylist]]
[ ;ACCESS=[fileaccess]]
[ ;ONVS=volumesetname][ ;HOMEVS=volumesetname]
NEWGROUP G2.GRIMSBY; CAP=PH,MR
```

NEWJOBQ

Creates a job queue.

```
NEWJOBQ qname[ ;LIMIT=n]
```

NEWUSER

Defines a new user.

```
NEWUSER username [.acctname][ ;PASS=[password]]
[ ;CAP=[capabilitylist]]
[ ;MAXPRI=[subqueuename]][ ;LOCATTR=[localattribute]]
[ ;HOME=[homegroupname]][ ;UID=[uid]]
NEWUSER LHSMITH;PASS=SMITTY;HOME=HOME GPX
NEWUSER LHSMITH;UID=120;PASS=SMITTY;HOME=HOME GPX
```

OCTCOMP

Converts a compiled MPE V/E program into native mode (NM) code for the 900 Series HP 3000.

```
OCTCOMP [input] [, [targetfile]][, [list]][ ;INFO=quotedstring]]
or
OCTCOMP [input] [, [targetfile]][, [list]][, [INFO=]quotedstring]]]
OCTCOMP SOURCEIN,OCTOUT;INFO="TRANS=1,2,3,4"
```

OPENQ

Opens the spool queue for a specified logical device or device class.

```
OPENQ {ldev [ ;SHOW]
       devclass [ ;SHOW]
       devname [ ;SHOW]
       @ }
OPENQ 6 ;SHOW
```

OPTION

This command modifies the environment of user defined commands and command files. It is used within the command definition to set up and change the environment dynamically.

```
OPTION [LIST
        NOLIST] [,] [RECURSION
                    NORECURSION]
OPTION LIST
```

OUTFENCE

Defines the minimum priority that an output spoolfile needs in order to be printed.

```
OUTFENCE outputpriority [ ;LDEV=ldev] [ ;DEV= {dev
                                                devclass
                                                devname } ]
OUTFENCE 14
OUTFENCE 7 ;LDEV=6
```

PASCAL

Compiles a compatibility mode Pascal/V program. The native mode equivalent of this command is PASXL.

```
PASCAL [textfile][ , [uslfile][ , listfile]][ ;INFO=quotedstring]
PASCAL PASC SRC , PASC OBJ , LIST FILE
```

PASCALGO

Compiles, prepares, and executes a compatibility mode Pascal/V program. The native mode equivalent of this command is PASXLGO.

```
PASCALGO [textfile][ , listfile][ ;INFO=quotedstring]
PASCALGO PASC SRC , LIST FILE
```

PASCALPREP

Compiles and prepares a compatibility mode Pascal/V program. The native mode equivalent of this command is PASXLK.

```
PASCALPREP [textfile][ , progfile][ , listfile][ ;INFO=quotedstring]
PASCALPREP PASC SRC , PASC PROG
```

PASXL

Compiles an HP Pascal/iX program.

```
PASXL [textfile][ , [objectfile][ , [listfile][ , libfile]]]
[ ; INFO=quotedstring]
PASXL MAIN, OBJMAIN
PASXL SUB, OBJSUB
LINK FROM=OBJMAIN, OBJSUB; TO=SOMEPROG
RUN SOMEPROG
```

PASXLGO

Compiles, links, and executes an HP Pascal/iX program.

```
PASXLGO [textfile][ , [listfile][ , [libfile]]][ ; INFO=quotedstring]
PASXLGO SOURCE, LISTFILE
```

PASLLK

Compiles and links an HP Pascal/iX program.

```
PASLLK [textfile][ , [progfile][ , [listfile][ , libfile]]]
[ ; INFO=quotedstring]
PASLLK SOURCE, PROG
```

PAUSE

Allows the user to suspend current activity for a specified number of seconds, or until one or more jobs complete.

```
PAUSE [num_seconds] [ ; JOB=jobid] [ ; INTERVAL=interval_secs] [ ; EXIST | WAIT | NOTEXIST]

STREAM JLOGEND
#J123
PAUSE JOB=!HPLASTJOB
```

PLISTF (UDC)

The PLISTF UDC executes the LISTFILE command to list descriptions of one or more disk files.

NOTE	System-defined UDCs are not automatically available. Your System Manager must use the SETCATALOG command to make these UDCs available for your use. For example:
-------------	--

```
SETCATALOG HPPXUDC.PUB.SYS
```

NOTE	If the PLISTF UDC is cataloged, it will override the LISTF command.
-------------	---

Syntax

```
PLISTF [filesset] [ , format_opt] [ ; outfile]
```

PREP

Prepares a compatibility mode program from a user subprogram library (USL) file onto a program file.

```
PREP uslfile, progfile [ ; ZERO DB] [ ; CAP=capabilitylist] [ ; PMAP]
[ ; RL=filename]
[ ; MAXDATA=segsize] [ ; PATCH=patchsize] [ ; STACK=stacksize]
[ ; DL=dlsiz e]
```

Commands Syntax

```
[ ;NOSYM ] [ ;FPMAP
                ;NOFPMAP ]
PREP USLX,PROGX
SAVE PROGX
```

PREPRUN

Prepares and executes a compiled compatibility mode program.

```
PREPRUN ustfile [ ,entrypoint ] [ ;NOPRIV ] [ ;RL=filename ] [ ;PMAP ]
[ ;NOCB ] [ ;DEBUG ]

[ ;INFO=quotedstring ] [ ;LMAP [ ;STDIN [ *formaldesig
                                     =fileref
                                     $NULL ] ] ]
[ ;MAXDATA=segsz ]
[ ;PARAM=parameternum ] [ ;STDLIST = [ *formaldesig
                                         fileref [ ,NEW ]
                                         $NULL ] ]
[ ;STACK=stacksize ] [ ;DL=dlsz ] [ ;PATCH=patchsize ]

[ ;LIB = { G
           P
           S } ] [ ;NOSYM ] [ { ;FPMAP
                               ;NOFPMAP } ] [ ;CAP=capabilitylist ]
PREPRUN XUSL;PMAP;LMAP
```

PRINT

Prints the contents of a file.

```
PRINT [ [ FILE = ] filename ] [ ; [ OUT = ] outfile ] [ ; [ START = ] m ]
[ ; [ END = ] n ] [ ; [ PAGE = ] p ] [ ; { UNN NUM } ] [ ;NONOM ]
PRINT MYFILE;OUT=XXY
PRINT ./posix/doc/print.doc;start=-10
```

PURGE

Deletes a file from the system.

```
PURGE filereference [ ;TEMP ]
[ ;ONLOCKWORD = SELECT | SKIP ]
[ ;ONERROR = CONTINUE | QUIT ]
[ ;NOAUTOLOCKWORD | LOCKWORD ]
[ ;CONFIRM ;NOCONFIRM | ;CONFIRMALL ]
[ ;SHOW | ;NOSHOW ]
PURGE PFILE,TEMP
PURGE ./posix/DOC/print.doc
```

PURGEACCT

Removes an account and its groups and users from the system directory or from the specified volume set's directory.

```
PURGEACCT acctname [ ;ONVS=volumesetname ]
PURGEACCT ACCT1
ACCT ACCT1 TO BE PURGED? YES
```

PURGEDIR

Purges (unlinks) one or more directories.

Syntax

```
PURGEDIR [dir=dir_name [; CONFIRM | NOCONFIRM ]
[; TREE | NOTREE | USENAME ] [; SHOW | NOSHOW]
[; SHOWERRORS | NOSHOWERRORS]
PURGEDIR /MYACCT/MYGRP/dir1
PURGEDIR /MYACCT/MYGRP/dir1;NOTREE
PURGEDIR /MYACCT/MYGRP/dir1/
PURGEDIR /MYACCT/MYGRP/dir1 ;TREE
```

PURGEGROUP

Removes a group (and all files belonging to it) from the system, or from the specified volume set directory.

```
PURGEGROUP groupname [ .acctname ] [ ; ONVS=volumesetname ]
PURGEGROUP GROUP1
GROUP GROUP1 TO BE PURGED? YES
```

PURGEJOBQ

Removes a job queue

```
PURGEJOBQ qname
```

PURGELINK

This command removes a link.

```
PURGELINK [LINK=] linkname
PURGELINK PAYROLL
PURGELINK /dira/scripts
```

PURGEUSER

Removes a user from an account.

```
PURGEUSER user [ .acctname ]
PURGEUSER USER1
USER USER1 TO BE PURGED? YES
```

RECALL /=RECALL

Displays all pending console REPLY messages.

```
RECALL
=RECALL
RECALL
THE FOLLOWING REPLIES ARE PENDING:
10:05/#J19/15/LDEV # FOR "L00576" ON TAPE1600 (NUM)?
```

REDO

Allows the user to edit and reexecute any command still retained in the command line history stack.

```
REDO [ [CMD=]cmdid] [ [;EDIT=]editstring ]
REDO 10
```

REFUSE

Disables jobs/sessions and/or data on a designated device.

```
REFUSE [JOBS,][DATA,]ldev  
REFUSE DATA,35
```

RELEASE

Releases a file from file access matrix access control. This command does not affect access control defined by lockwords or access control definitions (ACDs). It cannot be used on directories.

The file matrix access is not enforced until the file is secured with the MPE/iX `SECURE` command.

```
RELEASE filereference  
RELEASE FILE1
```

RELLOG

Removes a user logging identifier from the system.

```
RELLOG logid  
RELLOG DATALOG
```

RENAME

Changes identity (file name, lockword, and/or group name) of a disk file.

```
RENAME oldfilereference,newfilereference[ ,TEMP]  
RENAME OLDFILE,NEWFILE/LOCKW.NEWG.NEWACCT ,TEMP  
RENAME FILE2/LOCKA,FILE2/LOCKB  
RENAME MYFILE.GROUP1,MYFILE.GROUP2
```

REPLY/=REPLY

Replies to pending resource requests at the console.

```
REPLY pin,reply  
=REPLY pin,reply  
10:05/#J19/15/LDEV# FOR "NAS" OF TAPE1600 (NUM)?  
REPLY 15,7
```

REPORT

Displays accounting information for the logon account and group. Any user may obtain `REPORT` information about the user's logon group.

```
REPORT [groupset][ ,listfile][ ;ONVS=[volumesetname] ]  
REPORT SOPRM
```

RESET

Cancels file equations.

```
RESET {formaldesignator  
@}  
RESET ALPHA
```

RESETACCT

Resets the running counts of CPU time or connect time accumulated by an account and by all groups within that account to zero.

```
RESETACCT [ [ @
             acct ] [ , [ CPU
                       CONNECT ] ] ]
RESETACCT @, CPU
```

RESETDUMP

Disarms the debug call that is made during abnormal process termination.

```
RESETDUMP
RESETDUMP
```

RESTORE

Returns files that have been stored on magnetic tape to the system.

```
RESTORE [ restorefile ] [ ; filesetlist ] [ ; option [ ; ... ] ]
```

where *option* is:

```
[ ; DEV=device ] [ ; SHOW [=showoption [ , showoption [ , ... ] ] ] ]
[ ; FILES=maxfiles ]

[ ; { LOCAL
      GROUP=groupname
      ACC[oun]T=accountname } [ ; ... ] ]
[ ; CREATE [= { GROUP
               ACCOUNT
               CREATOR } [ , ... ] ] ]
[ ; CREATOR [=username ] ] [ ; { KEEP
                               NOKEEP } ] [ ; { OLDDATE
                                               NEWDATE } ] ]

[ ; ONERR[or] = { QUIT
                 SKIP } ]
[ ; DIRECTORY ] [ ; LISTDIR ] [ ; FC RANGE=filecode/filecode [ , ... ] ]
[ ; VOLSET=volumesetname ] [ ; VOL=volumename ]
[ ; VOLCLASS=volumeclassname ]
FILE T ; DEV=TAPE
RESTORE *T ; @ ; KEEP ; SHOW
```

RESUME

Resumes execution of a suspended operation.

```
RESUME
RESUME
READ PENDING
Return
```

RESUMEJOB

Resumes a suspended job.

```
RESUMEJOB #Jnnn
RESUMEJOB #J68
```

RESUMELOG

Resumes system logging following suspension caused by an error.

Commands Syntax

```
RESUMELOG
ST/10:43/LOG FILE NUMBER 104 ERROR #46.
LOGGING SUSPENDED.
RESUMELOG
ST/10:45/LOG FILE NUMBER 104. LOGGING RESUMED.
ST/10:45/LOG FILE NUMBER 104 ON.
```

RESUMESPOOL

Resumes suspended spooler output to a spooled device.

```
RESUMESPOOL ldev{ ;BACK [nnn FILES
                   nnn PAGES]
                 ;FORWARD [nnn FILES
                           nnn PAGES]
                 ;BEGINNING }
RESUMESPOOL 6;BEGINNING
```

RETURN

Causes execution to return from the current user command (UDC or command file) to the calling environment.

```
RETURN
RETURN
```

RPG

Compiles an RPG/V program in compatibility mode.

```
RPG [textfile][, [uslfile][, [listfile][, [masterfile][, [newfile]]]]]
BUILD OBJECT;CODE=USL
RPG SOURCE,OBJECT,LISTFL
```

RPGGO

Compiles, prepares, and executes an RPG/V program in compatibility mode.

```
RPGGO [textfile][, [listfile][, [masterfile][, [newfile]]]]]
RPGGO SOURCE,LISTFL
```

RPGPREP

Compiles and prepares an RPG/V program in compatibility mode.

```
RPGPREP [textfile][, [progfile][, [listfile][, [masterfile][, [newfile]]]]]
RPGPREP,COMFL
SAVE $OLDPASS,NUSL
```

RPGXL

Compiles an RPG/XL program.

```
RPGXL [textfile][, [objectfile][, [listfile]]] [ ;INFO=quotedstring ]
RPGXL RPGSRC,MYRPGOBJ,LISTFILE
```

RPGXLGO

Compiles, links, and executes an RPG/XL program.

```
RPGXLGO [ textfile ] [ , listfile ]
RPGXLGO RPGSRC,LISTFILE
```

RPGXLLK

Compiles and links an RPG/XL program.

```
RPGXLLK [ textfile ] [ , [ progfile ] [ , listfile ] ]
RPGXLLK RPGSRC,RPGPROG
```

RUN

Executes a prepared or linked program.

```
RUN progfile [ , [ " ] entrypoint [ " ] ] [ ;NOPRIV ] [ ;LMAP ] [ ;DEBUG ]
[ ;MAXDATA=maxstack ] [ ;PARM=parameternum ]
[ ;STACK=stacksize ] [ ;DL=dlsize ] [ ;NMSTACK=nmstacksize ]
[ ;NMHEAP=nmheapsize ]
[ ;LIB= { G
        P
        S } ] [ ;XL=" library [ , . . . ] " ] [ ;NOCB ]
[ ;INFO=" quotedstring " ]
[ ;UNSAT=[ ` ` ] unsatproc [ ` ` ] ] [ ;STDIN=[ *formaldesig
                                     fileref
                                     $NULL ] ]
[ ;STDLIST=[ *formaldesig
             fileref [ ,NEW ]
             $NULL ] ] [ ;PRI= { BS
                               CS
                               DS
                               ES } { # } ]

RUN TESTPROG;DEBUG;STDIN=*INFILE;STDLIST=RESULTS,NEW
```

SAVE

Saves a file in the permanent system file domain.

```
SAVE { $OLDPASS, newfilereference
      tempfilereference
      }

SAVE $OLDPASS,PROGFILE
SAVE TEMPFL
SAVE DATAFILE.GROUPX
```

SECURE

Restores file access matrix access control for a file. The RELEASE command suspends file access matrix access control. Enabling the file access matrix does not have an immediate effect on file access if the file is protected by an ACD. ACDs override the file access matrix.

```
SECURE filereference
SECURE FILE1
```

OR

```
SECURE ./FILE1
```

SEGMENTER

Starts the MPE segmenter.

Commands Syntax

```
SEGMENTER [listfile]

FILE LISTFL;DEV=LP
SEGMENTER *LISTFL
```

SET

Defines elements of the command interpreter. It also allows a job using a spooled \$STDLIST to mark its standard list device for deletion when the job terminates.

```
SET [STDLIST={DELETE
          SAVE}][;ECHO={ON
                      OFF}][;MSG={ON
                                   OFF}]

[;SPEED={300
          1200
          2400
          4800
          9600
          19200
          19.2K}]

!JOB EXAMPLE, USER.TECHPUB,XGROUP
!CONTINUE
!RUN UPDATE.PUB.SYS;PARM=1;MAXDATA=16000
!IF JCW < FATAL THEN
!SET STDLIST=DELETE
!ENDIF
!EOJ
```

SETCATALOG

Causes the command interpreter to search a catalog of user defined commands (UDCs) and to establish a directory entry for each command, or to clear the previous catalog.

```
SETCATALOG [catfilename [, catfilename , ... [, catfilename ]]] [;SHOW]
[;SYSTEM]
[;ACCOUNT][;USER=username [.acctname ]][;RESET][;APPEND]
[;DELETE]

SETCATALOG UDCA,UDCB
SETCATALOG UDCA
SETCATALOG UDCE;APPEND
SETCATALOG
```

SETCLOCK

Alters the system time or system time zone.

```
SETCLOCK {DATE= date spec ; TIME= time spec [;GRADUAL
                                         ;NOW]
          CORRECTION= correction spec
          TIMEZONE= time zone spec
          ;CANCEL}

:SETCLOCK DATE=07/04/1993;TIME=15:00
:SETCLOCK CORRECTION= +3600
```

SETDUMP

Arms the system DEBUG facility for a process abort.

```
SETDUMP [DB[ ,ST[ ,QS]]][;ASCII][;DEBUG="commands" ]

SETDUMP
```

SETJCW

Creates or assigns a value to a job control word (JCW) variable.

```
SETJCW jcwname delimiter value [ {+
                                     -} value ]

SETJCW CURR1,100
SETJCW CURR1/WARN
SETJCW NEWJCW=LASTJCW + 56
```

SETMSG

Enables or disables the receipt of user or operator messages at the standard list device.

```
SETMSG {OFF
        ON }

SETMSG OFF
SETMSG ON
```

SETVAR

Assigns values to MPE/iX variables.

```
SETVAR varname{ expression
                 ,expression
                 ;expression }

SETVAR HPPROMPT " !HPUSER. !HPACCOUNT: "
```

SHOWALLOW

Displays which operator commands have been allowed.

```
SHOWALLOW [ user.acct
            user:@
            @ acct
            @. @ ]

SHOWALLOW USER.SYS
```

SHOWCATALOG

Displays information about user defined commands (UDCs).

```
SHOWCATALOG [ listfile ] [ ;USER=username [ .acctname ] ]

SHOWCATALOG ;USER=@.GRIMSBY
```

SHOWCLOCK

Displays information about the system date and time.

```
SHOWCLOCK

:SHOWCLOCK

SYSTEM TIME: FRI, JUL 24, 1987, 8:47:35 AM
CURRENT TIME CORRECTION: -3428 seconds
TIME ZONE: 7 HOURS 0 MINUTES WESTERN HEMISPHERE
```

SHOWDEV

Reports the status of input/output devices.

```
SHOWDEV [ldev
         classname]

SHOWDEV 5
```

SHOWIN

Reports the status of input device files.

```
SHOWIN [#Innn
        STATUS
        SP
        item [;item [;...]]]
```

Where *item* is:

```
[DEV=ldev ] [JOB= {@J
                  @S
                  @
                  [ #]Jnnn
                  [ #]Snnn}]

[ACTIVE
 OPENED
 READY ]

SHOWIN JOB=@S;OPENED
```

SHOWJCW

Displays the current state of one or more job control word (JCW) variables.

```
SHOWJCW [jcwname]

SHOWJCW JCW1
```

SHOWJOB

Displays status information about jobs/sessions.

```
SHOWJOB [ [#]Snnn
          [#]Jnnn
          STATUS
          SCHED
          item [;item [;...]] [;*listfile]
          [;JOBQ]
```

Where *item* is:

```
[JOB={@J
       @S
       @
       [jsname , username.acctname] } [;INTRO
                                       ;EXEC
                                       ;SUSP
                                       ;WAIT [,N
                                       ,D] ]

SHOWJOB STATUS
```

SHOWLOG

Displays the number of the system's current log file and the percentage of disk space used.

```
SHOWLOG
SHOWLOG
```

SHOWLOGSTATUS

Displays status information about currently opened user logging files assigned to a logging identifier.

```
SHOWLOGSTATUS [logid]
SHOWLOGSTATUS LEN
```

SHOWME

Reports job/session status.

```
SHOWME
SHOWME
```

SHOWOUT

Displays the status of output device files.

```
SHOWOUT [#Onnn
        STATUS
        SP
        item[ ;item[ ; . . . ]]]
```

Where *item* is:

```
[DEV={ldev
      classname}][JOB= {@J
                       @S
                       @
                       [#]Jnnn
                       [#]Snnn }][ACTIVE
                                  OPENED
                                  LOCKED
                                  READY [ ,N
                                          ,D]]

SHOWOUT STATUS
SHOWOUT #0111
```

SHOWPROC

Displays information about one or more processes. (**Native Mode**)

```
SHOWPROC [ [ ;PIN=] {pinspec(pinspec [ ,pinspec] . . . )}
           [ ;JOB=] {jobspec(jobspec [ ,jobspec] . . . )}] [ . . . ]
[ [ ;FORMAT=] SUMMARY | DETAIL] [ ;TREE | ;NOTREE]

[ ;USER | ;ANYUSER][ ;SYSTEM]

SHOWPROC 1 ;SYSTEM ;TREE Show ALL processes if user has SM.
SHOWPROC 42 ,#J3 ;TREE Show process information for pin 42
                        and for job 3 and its descendants.
SHOWPROC JOB=@J ;ANYUSER Show all jobs to SM or OP user.
SHOWPROC (150 ,#P247 ,211) Show process information for pins 150, 247, 211.
```

SHOWQ

Displays process scheduling data and the contents of each subqueue. System supervisor (OP) capability is required to use this command.

```
SHOWQ [ ;ACTIVE ] [ ;STATUS ]
```

```
SHOWQ
```

SHOWTIME

Prints current time and date.

```
SHOWTIME
```

```
SHOWTIME
```

SHOWVAR

Displays specific variable names and their current values.

```
SHOWVAR [ varid ] [ , varid ] . . . [ , varid ] [ ;JOB=jobid ] [ ;HP | USER | ANY ]
```

```
SHOWVAR firstvariable, secondvariable
```

=SHUTDOWN

Initiates a shutdown of MPE/iX.

```
=SHUTDOWN [ system  
          terminal  
          dtc  
          tape  
          disk  
          network  
          other ]
```

```
CTRL]] A]]
```

```
=SHUTDOWN
```

```
CTRL]] A]]
```

```
=SHUTDOWN dtc
```

SHUTQ

Closes the spool queue for the specified logical device or device class.

```
SHUTQ { ldev [ ;SHOW ]  
      devclass [ ;SHOW ]  
      devname [ ;SHOW ]  
      @ }
```

```
SHUTQ @
```

```
SHUTQ 6 ;SHOW
```

SPEED

Sets the input and output speed for the user's terminal.

```
SPEED newinspeed, newoutspeed
```

```
or
```

```
SET SPEED = newspeed
```

```
SPEED 240,240
or
SET SPEED=2400
```

SPL

Compiles a compatibility mode SPL/V program.

```
SPL [textfile][, [usfile][, [listfile][, [masterfile][, newfile]]]]
[; INFO=quotedstring]
```

```
SPL SOURCE,OBJECT,LISTFL
SAVE OBJECT
```

SPLGO

Compiles, prepares, and executes a compatibility mode SPL/V program.

```
SPLGO [textfile][, [listfile][, [masterfile][, newfile]]]
[; INFO=quotedstring]
```

```
SPLGO SOURCE,LISTFL
```

SPLPREP

Compiles and prepares a compatibility mode SPL/V program.

```
SPLPREP [textfile][, [progfile][, [listfile][, [masterfile][, newfile]]]]
[; INFO=quotedstring]
```

```
SPLPREP SFILE,MYPROG
```

SPOOLER

Controls spooler processes.

```
SPOOLER [DEV=]{ldev
                devclass
                devname}
{; SHOW
; OPENQ [; SHOW]
; SHUTQ [; SHOW]
; START [; OPENQ
        ; SHUTQ] [; SHOW]
; STOP [; FINISH
        ; NOW] [; OPENQ
        ; SHUTQ] [; SHOW]
; SUSPEND [ [; FINISH
            ; NOW] [; NOKEEP
            ; KEEP]
            [; OFFSET=[+
              -]page]
            [; OPENQ
            ; SHUTQ] [; SHOW] ]
; RESUME [; OFFSET=[+
          -]page] [; OPENQ
                ; SHUTQ] [; SHOW]
; RELEASE [; OFFSET=[+
           -]page][; OPENQ
            ; SHUTQ] [; SHOW]}
```

```
SPOOLER dev;SUSPEND;NOKEEP;OFFSET=1
SPOOLER dev;SUSPEND;KEEP;OFFSET=-3
SPOOLER dev;RESUME;OFFSET=-6
SPOOLER LP;SHOW
```

SPOOLF

Allows a qualified user to alter, print, or delete output spoolfile(s). (**Native Mode**)

```
SPOOLF  {[ [IDNAME=] {spoolid
              (spoolid[ , spoolid]. . . .)}
          [ ;ALTER]      [ ;SELEQ= { [select-eq
              ^indirect_file]}
          [ ;DEV={ldev
              devclass
              devname}]
          [ ;PRI=outpri] [ ;COPIES= numcopies]
          [ ;SPSAVE]    [ ;DEFER
              ;UNDEFER] [ ;SHOW] ]
      [ [IDNAME=] {fileset
              (fileset[ , fileset]. . . .)}
          [ ;PRINT] [ ;DEV= {ldev
              devclass
              devname}]
          [ ;PRI=outpri] [ ;COPIES= numcopies]
          [ ;SPSAVE]    [ ;DEFER
              ;UNDEFER] [ ;SHOW] ]
      [ [IDNAME=] {spoolid
              (spoolid[ , spoolid]. . . .)}
          [ ;DELETE] [ ;SELEQ= {select-eq
              ^indirect_file]}
          [ ;SHOW] ] }
```

Where the select equation, *enclosed in square brackets*, has the following syntax:

```
select_eq ::= [equation]
equation ::= {parm{ >
              >=
              <
              <=
              <>
              = } value
              NOT (equation)
              (equation) {AND
                          OR} (equation) }
```

```
SPOOLF O@;SELEQ=[DEV=16];ALTER;PRI=8;SHOW
```

STARTSESS

Creates a session on the specified device, if the user has programmatic sessions (PS) capability.

```
STARTSESS ldev; [sessionname, ]user[ /userpass].acct[ /acctpass]
[ ,group[ /grouppass]]
[ ;TERM={termtype}][ ;TIME=cpusecs][ ;PRI= {BS
                                             CS
                                             DS
                                             ES}]
[ ;INPRI=inputpriority
  ;HIPRI]
[ ;NOWAIT] [ ;INFO=ciinfo] [ ;PARM=ciparm]
STARTSESS 28;USER.GROUP.ACCOUNT
```

STARTSPOOL

Initiates the spooler process for a device.

```
STARTSPOOL [ {ldev[ ;SHUTQ]
              devclass } ]
STARTSPOOL 6;SHUTQ
```

STOPSPPOOL

Terminates spooling to a specified device or device class.

```
STOPSPPOOL [ {ldev[ ;OPENQ]
              devclass      } ]

STOPSPPOOL 6;OPENQ
```

STORE

Copies disk files onto a magnetic tape. Files copied to tape with the STORE command can be recovered with the RESTORE command.

```
STORE [fileselist][ ; [storefile][ ; option[ ; option[ ; ... ]]]]
```

where *option* is:

```
[ ; SHOW[=showparmlist] ] [ ; ONERROR=recoverytype ] [ ; FILES=maxfiles ]
[ ; DATE<=accdte ]
[ ; DATE>=moddate ] [ ; PURGE ] [ ; PROGRESS [=minutes] ]
[ ; FCRRANGE=filecode/filecode[ , ... ] ] [ ; DIRECTORY ] [ ; TRANSPORT ]
[ ; SPLITVS=split_setname[ , split_setname[ ... ] ] ]
[ ; ONVS=volumesetname[ , volumesetname[ ... ] ] ] [ ; MAXTAPEBUF ]
[ ; COPYACD ] [ ; NOACD ] [ ; RENAME ]
```

The *fileselist* parameter has the following form:

```
filesesitem[ , filesesitem[ ... ] ]
```

where *filesesitem* may be **!!indirectfile**, **!!^indirectfile**, *fileses*.

The *fileses* parameter has the following form:

```
filestostore[ -filestoexclude[ -filestoexclude[ - ... ] ] ]

FILE DEST;DEV=TAPE
STORE @.GP4X;*BACKUP;SHOW;TRANSPORT
FILE SYSLIST;DEV=LP
; SPLITVS = SPLIT_SETNAME[,SPLIT_SETNAME ... ]
STORE @.@.*;*REEL;ONVS=VOLMINE
STORE @.GP4X;*BACKUP;SHOW
FILE T;DEV=TAPE
STORE INDFILE;*T ** OR ^INDFILE;*T **
STORE @.GROUP.ACCOUNT
STORE myset[d-e 1-6]
STORE
STORE @.@.-@.@.SYS;*TAP;SHOW=SECURITY,DATES,LONG&
STORE @.GROUP.ACCOUNT;PURGE
STORE PROG@.VERSION#.PRODACCT=@.@.ARCHIVE:CREATOR;*T;RENAME
```

STREAM

Spools batch jobs or data from a session or job. The optional time-related parameters of the STREAM command may be used to schedule jobs.

```
STREAM [filename] [ , char ] [ ; AT = timespec ]
[ ; DAY = { day-of-week
           day-of-month
           days-until-month } ]
[ ; DATE = datespec ] [ ; IN = [ days[ , [ hours ] [ , minutes ] ] ] ] [ ; JOBQ=queuname ]

STREAM JOBFIL;IN=1,8
```

STREAMS

Enables or disables the STREAMS device. Allows or disallows users to submit job/data streams.

```
STREAMS {ldev  
        OFF }
```

```
STREAMS 10
```

SUSPENDSPOOL

Suspends output to a spooled device.

```
SUSPENDSPOOL ldev[:FINISH]
```

```
SUSPENDSPOOL 6;FINISH
```

SWITCHLOG

Closes the current system log file, then creates and opens a new one.

```
SWITCHLOG
```

```
SWITCHLOG
```

SYSGEN

Starts configuration dialog and/or installation tape creation. This command replaces the SYSDUMP command, which is no longer supported.

```
SYSGEN [basegroup][, newgroup][, inputfile][, outputfile]
```

```
SYSGEN CONFIG,NEWCONF,$STDIN,$STDLIST
```

TELL

Sends a message to another session.

```
TELL {[#]Snnn  
      [sessionname,] username.acctname  
      @  
      @.acctname  
      @S }[[:]text]
```

```
TELL @.A PLEASE LOG OFF
```

TELLOP

Sends a message to the system console.

```
TELLOP [text]
```

```
TELLOP PLS MOUNT MYTAPE,VERSION 1
```

TUNE

Changes the filter and/or priority limits of circular subqueues.

```
TUNE [mincycle] [[:CQ=qinfo  
                  :DQ=qinfo  
                  :EQ=qinfo] [ ... ]
```

Where *qinfo* is written in the following form:

```
[base [, [limit][, [min][, [max][, DECAY
, OSCILLATE]]]]]
TUNE CQ=152,200,,300;DQ=202,238,1000,1000,OSCILLATE
```

UP

Returns a particular device to its normal function on the system; cancels any DOWN command issued for the device. This command does not apply to disks.

```
UP ldev
UP 10
```

VMOUNT

Enables or disables the MPE/iX movable volume facility.

```
VMOUNT {ON [,AUTO]
OFF} [;ALL]
VMOUNT OFF;ALL
```

VSCLOSE

Informs the system to close the specified volume set and take it offline. **(Native Mode)**

```
VSCLOSE volumesetname [ [;PARTVS=] {USER
BACKUP}} [;NOW
;SPLIT]
VSCLOSE ACCOUNTING_PAYROLL
VSRELEASESYS ACCOUNTING_PAYROLL
VSCLOSE ACCOUNTING_PAYROLL
```

VSOPEN

Reopens a volume set that has been closed with VSCLOSE. The volume set becomes available for use again. **(Native Mode)**

```
VSOPEN volumesetname[ [;PARTVS=] {USER
BACKUP}]
VSOPEN ACCOUNTING_PAYROLL
```

VSRELEASE

Releases a volume set that was explicitly reserved by the user with VSRESERVE. The equivalent compatibility mode command is DISMOUNT.

```
VSRELEASE [volumesetname]
VSRELEASE ACCOUNTING_PAYROLL
```

VSRELEASESYS

Negates a previously issued VSRESERVESYS for the specified volume set. The equivalent compatibility mode command is LDISMOUNT.

Commands Syntax

```
VSRELEASESYS volumesetname
VSRELEASESYS ACCOUNTING_PAYROLL
```

VSRESERVE

Notifies the system to keep a particular volume set on line. The equivalent compatibility mode command is MOUNT.

```
VSRESERVE [volumesetname] [ ;GEN=genindex]
VSRESERVE ACCOUNTING_PAYROLL
```

VSRESERVESYS

Instructs the system to reserve a volume set online system-wide. The equivalent compatibility mode command is LMOUNT.

```
VSRESERVESYS volumesetname
VSRESERVESYS ACCOUNTING_PAYROLL
```

VSTORE

Verifies that the data on a backup media are valid (for example, there are no media errors) and reports errors incurred by STORE when writing the tape. VSTORE only applies to NMSTORE tapes created in native mode. It does not work on tapes created in compatibility mode. (*Native Mode*)

```
VSTORE vstorefile [ ;[fileselist][option [ ;... ]]]
```

Where *option* has the following format:

```
[ ;SHOW=[showoption[ ,showoption[ ,... ]]]]
[ ;ONERR[OR]={QUIT
                SKIP
                FULL}} [ ;LOCAL][ ;DIRECTORY]

VSTORE *T;@.@.@; SHOW = OFFLINEV
FILE SYSLIST;DEV=LP
FILE T; DEV=TAPE
VSTORE *T; @.@.@
VSTORE *T;@.@.@; SHOW=OFFLINE
```

VSUSER

Lists all users of a currently reserved, mountable volume set.

```
VSUSER [volumesetname]

VSUSER
```

WARN

Sends an urgent message to jobs/sessions.

```
WARN {@
      [#]Jnnn
      [#]Snnn
      [jsname , user.acct] [ ;message ]
```

```
WARN @;THE SYSTEM WILL SHUTDOWN IN 5 MINUTES. PLS LOG OFF.  
WARN #S51;LAST CHANCE TO LOG OFF GRACEFULLY.
```

WELCOME

Defines the welcome message.

```
WELCOME [welcfile]  
  
WELCOME  
#WELCOME TO THE HP3000 COMPUTER SYSTEM.  
#FILES WILL BE STORED EACH DAY BETWEEN 6AM AND 7AM.  
#Return]]
```

WHILE

Used to control the execution sequence of a job, UDC, or command file.

```
WHILE expression[DO]  
  
WHILE SETVAR  
:  
:  
:  
ENDWHILE
```

XEQ

Executes any program or command file.

```
XEQ filename [parameterlist] *
```

OR

```
XEQ filename [ ;INFO=quotedstring][ ;PARM=parmvalue] **
```

```
* for command files  
** for program files
```

```
XEQ fcopy
```


2 Utilities

Utilities Descriptions

Brief descriptions of the utilities available for MPE/iX.

ASOCTBL

Use the ASOCTBL utility to distribute operator commands for specific devices to standard MPE/iX users. This utility creates a table that associates users with device classes in a file called ASOCIATE.PUB.SYS. Users gain access to the corresponding device class with the ASSOCIATE command. The user then has exclusive access to the operator commands that control that device until their association is terminated by logging off or issuing the DISASSOCIATE command. In ASOCTBL, > is the prompt.

```
ASOCTBL                               or                               RUN ASOCTBL.PUB.SYS
>devclass=username.acctname|         >devclass=username.acctname|
```

AUTOINST

AUTOINST restores the information contained on the FOS and SUBSYS tapes, sets up the necessary account structure, and creates a customized system load tape (SLT).

```
AUTOINST
```

BULDACCT

BULDACCT runs only on MPE/iX. Use it to take a snapshot of the directory structure on the source system, then recreate it on the destination system. Use BULDACCT to migrate a set of accounts from one volume set to another.

BULDACCT has been enhanced to work with MPE/iX hierarchical directory structures. The hierarchical directory information for accounts, groups, and users is written to BULDJOB1. BULDJOB1 contains the commands used to recreate hierarchical directories and the ACDs associated with each of them.

```
BULDACCT;INFO="processing_options"   or                               BULDACCT
BULDACCT:processing_options
```

BUILDINT

Use the BUILDINT utility to build or change compatibility mode (CM) intrinsic disk files. BUILDINT accepts SPL procedure head declarations (OPTION EXTERNAL is required) and optional commands as input data. If no commands are issued, the procedure head declarations are added to the intrinsic file. Any input data that is not a procedure head terminates input; at this point, the program prints a formatted list of all intrinsics and terminates.

RUN BUILDINT.PUB.SYS OR BUILDINT

CLKUTIL

CLKUTIL reads and sets the hardware clock. The clock is used for timestamps and time displays. It is usually set to Greenwich Mean Time (GMT). CLKUTIL is a standalone utility, and runs only on the physical console at the ISL prompt.

ISL> CLKUTIL

DEBUG

DEBUG is used primarily by system programmers, who use it to set breakpoints within programs, and to display and modify data stacks and registers. Access through the DEBUG command is available only to users with privileged mode (PM) capability. Nonprivileged users can get limited access with the ;DEBUG option of the RUN command to debug their applications; the DEBUG utility will not allow them privileged access to the system.

DEBUG OR RUN PROGNAME;DEBUG

CAUTION Normal MPE safeguards are bypassed in privileged mode. When attempting to modify privileged data on disk, it is possible to destroy file integrity, or the MPE operating system itself. Hewlett-Packard is *not* responsible for changes you make to the operating system or system files. For more information, talk to your Hewlett-Packard service representative.

DIRMIG

DIRMIG (The Directory Migration Tool) utility simplifies the migration of your environment from MPE V/E systems to MPE/iX systems. DIRMIG uses an MPE V/E SYSDUMP tape to transport data including the system directory (account structure), UDCs, user logging IDs, user files and information specifically related to user volumes.

DIRMIG OR RUN DIRMIG.PUB.SYS

DISCFREE

The DISCFREE utility displays information about the system's free disk space, total volume space capacity, and disk allocation for single volumes or for the whole system. It also determines disk volume fragmentation and transient and permanent disk space limits. DISCFREE displays disk allocation data only for mounted MPE/iX volumes, not scratched volumes; use the DSTAT command to identify currently mounted volumes.

DISCFREE OR DISCFREE"[[format]][,ldev]"

or

```
RUN DISCFREE.PUB.SYS;INFO="[<\esc>format][,ldev]"
```

DISCUTIL

DISCUTIL is a standalone utility that you use to request various disk operations. Use it with the RECOVER command of VOLUTIL to save, and subsequently recover, files from a system that has become logically inoperable. This program can be invoked only at the Initial System Load prompt (ISL>).

```
ISL> DISCUTIL
```

DUMP

The MPE/iX utility DUMP takes a snapshot or dump of system memory. It helps you, or HP support personnel, track down problems in system operation. To use, first request a non destructive boot; this saves the machine's hardware state. Then enter the DUMP command; this lets DUMP take control and dump the processor internal memory, main memory, and all allocated secondary storage marked as dumpworthy.

```
ISL>DUMP
```

EDIT/3000

EDIT/3000 creates and manipulates ASCII files. Use EDIT/3000 commands to insert, delete, replace, modify, search for, and manipulate individual characters, strings of characters, or entire lines of characters. EDIT/3000 can be run in interactive or batch mode.

```
EDITOR
```

FCOPY

Use FCOPY to copy and translate files. You identify the input file and output file. You can request one or more optional functions, such as converting data, copying files from other systems, appending files, extracting subsets of files, or displaying binary files in ASCII format.

The FCOPY utility can be copied from the HFS directories into accounts and groups. Files can be opened from HFS directories into existing files in other HFS directories.

```
FCOPY FROM=filename;TO=filename[;options]
```

In the following example, the file /dir1/doc/print.es is copied to the file myfile in the PUB group of the SYS account.

```
FILE FOO=/dir1/doc/print.es|FCOPY from=*FOO; to=myfile.pub.sys|
```

FSCHECK

The file system check utility (FSCHECK) is a native mode program for detecting and repairing inconsistencies found in the file directories and file label tables of the MPE/iX operating systems. It also provides the additional ability to query and display various attributes of these objects. It is a standalone utility and should be the only program running on the system when it is in use.

FSCHECK

WARNING	Do not use this utility without proper service center support. Unauthorized use will void you warranty and may cause data loss.
----------------	--

GENCAT

Use the GENCAT utility to modify a source catalog, or expand a formatted message catalog (for instance, a message catalog in the user's native language). You don't need any special capabilities to use it.

GENCAT OR RUN GENCAT.PUB.SYS

I7DB8CNV

I7DB8CNV converts the character data in an IMAGE data base from any Hewlett-Packard 7-bit national substitution set to ROMAN8. The program is a special version of the program DBLOAD.PUB.SYS and the conversion is done as part of a database load. Generally, DBUNLOAD.PUB.SYS and DBUTIL.PUB.SYS, ERASE are invoked before I7DB8CNV.

RUN I7DB8CNV.PUB.SYS

IOMAP

IOMAP is a standalone utility that identifies the actual configuration of the system and its paths and devices. Use it to map all existing I/O components in the system and to test I/O system components, using IOMAP's selftest and loopback diagnostics. Run IOMAP from the initial system loader (ISL) prompt; it can only be run on a down system. IOMAP shows processor identification (model, identification, processor board revisions, cache sizes, coprocessors, and main memory) and I/O configuration (paths and components for all cards). By comparing this information with system configuration information, you can see if the hardware that is physically available is the same as the hardware that is configured into the system. Also see SYSMAP.

ISL> IOMAP

KSAMUTIL

Use KSAMUTIL to manage compatibility mode Keyed Sequential Access Method (CM KSAM) files. You can create a CM KSAM file, rename both the data and key files, save a temporary file as a permanent file, clear all data from a file, purge a file, and verify the

contents and access history of an existing file. The file information may be displayed to the terminal or to a printer. `KSAMUTIL` runs either in session or in batch mode. You can issue MPE/iX commands within `KSAMUTIL`, if you put a colon (:) in front of the command name.

```
KSAMUTIL                OR                RUN KSAMUTIL.PUB.SYS
```

LANGINST

Use `LANGINST` to configure language-specific information onto your HP 3000. You must logon as `MANAGER.SYS` to run `LANGINST`. You can do the following tasks with `LANGINST`:

- Add a language to, or remove a language from, the configuration file.
- Display and modify local formats of a configured language.
- Display the languages supported by Hewlett-Packard.
- Display the language currently configured.
- Modify the system default language.

```
LANGINST
```

LINK EDITOR/XL

`Link Editor/XL` prepares native mode (NM) compiled object files for execution on 900 Series HP 3000 computers. You can also use `Link Editor/XL` to create and maintain relocatable and executable libraries. To invoke it and use it interactively, enter `LINKEDIT` at the MPE/iX prompt. Use the `RUN` command to invoke `Link Editor/XL` and specify an information string.

```
LINKEDIT
```

OR

```
RUN LINKEDIT.PUB.SYS;INFO=infostring
```

LOGGING (Security Auditing)

You can request that the operating system keep records of particular users, as well as particular events. A new log file is begun automatically every time you reboot. You can also request that a new file be started.

LOGTOOL

The System and Memory Log Analysis Tool (`LOGTOOL`) can manipulate two types of log files: system log files, and the memory log file. Functions on the various system log files include deleting/clearing the files and displaying their contents. Commands are executed immediately after they are received. `LOGTOOL` is available in multi-user mode, but some functions require a diagnostic security level.

```
SYSDIAG  
DUI> RUN LOGTOOL
```

MAKECAT

Use the MAKECAT utility to access, maintain, and change the following message catalogs:

- CATALOG.PUB.SYS, which contains system error messages.
- CICAT.PUB.SYS, which contains the HELP catalog.
- ser-defined catalogs for various applications.

```
RUN MAKECAT.PUB.SYS
```

N7MF8CNV

N7MF8CNV converts data in MPE text and data files, such as EDIT/XL files, from Hewlett-Packard 7-bit national substitution character set to ROMAN8. The user is prompted for language and file type (text or data). For a text file, each record is converted as one field. For a data file, the user will be prompted on each file for the starting position and length of each field (portion of a record) to be converted.

```
N7MF8CNV          or          RUN N7MF8CNV.PUB.SYS
```

NLIOUTIL

NLIOUTIL is used to dynamically activate the Native Language I/O (NLIO) subsystem for Asian and Middle East/African (MEA) peripheral devices (terminals and printers). NLIO is the basic input and output system integrated into the MPE/iX operating system for Native Language Support (NLS). Once activated by NLIOUTIL, properly configured native devices may use the Native Language I/O facility. Also see NMMGR.

```
NLIOUTIL          or          RUN NLIOUTIL.PUB.SYS;INFO=infostring
```

NLUTIL

NLUTIL is a utility program used to verify a variety of Native Language Support (NLS) languages and corresponding character sets available on the operating system. You can have a complete listing printed on the system printer; you can display a table showing the currently configured languages and their character set types.

```
NLUTIL            or          RUN NLUTIL.PUB.SYS
```

NMMGR

The Node Management Services Configuration Manager is a menu-driven utility you use to configure your HP 3000's data communications subsystems.

```
NMMGR
```


SAINT

SAINT is an interactive utility program that analyzes system libraries to produce executable images known as boot images. Its primary function is to produce a boot image for the operating system.

WARNING	Do not use this utility without service center support. Unauthorized use will void your warranty and may cause data loss.
----------------	--

SEGMENTER

SEGMENTER manages and prepares compatibility mode (CM) code segments. You can invoke it directly, with the SEGMENTER command. Use it to manage code segments in USL's (user subprogram libraries), RL's (relocatable libraries) and SL's (segmented libraries) and to group RBM's (relocatable binary modules) into code segments. Invoked indirectly (at PREP time), you can use SEGMENTER to define run-time parameters and to group CM program statements into RBM's and code segments with source program statements.

SEGMENTER

SLPATCH

SLPATCH displays or modifies the contents of a Segmented Library (SL) file. Also see SEGMENTER. Before using this utility you should be familiar with machine-executable instructions and the internal format of segmented library files in the HP 3000 system environment.

SLPATCH or RUN SLPATCH.PUB.SYS

CAUTION	SLPATCH bypasses normal MPE/iX safeguards and will modify the contents of privileged program files. When attempting to modify privileged data on disk, it is possible to destroy file integrity, or the MPE operating system itself. Hewlett-Packard is <i>not</i> responsible for changes you make to the operating system or system files. For more information, talk to your Hewlett-Packard service representative.
----------------	---

SOMPATCH

SOMPATCH is used for binary modification of a native mode spectrum object module (SOM) program or library file. Binary modification is referred to normally as patching. This utility also provides online help for command syntax and function.

WARNING	Do not use this utility without service center support. Unauthorized use will void your warranty and may cause data loss.
----------------	--

SORT-MERGE/XL

Use `SORT` to sort files based on single or multiple key items. You can sort data alphabetically, numerically, or in a collating sequence you define; you can request ascending or descending order. Use `MERGE` to merge data from two or more sorted files into a single, new file. `SORT-MERGE/XL` operates from within a program, or as a standalone utility in either interactive or batch mode.

```
SORT                OR      RUN SORT.PUB.SYS
MERGE               OR      RUN MERGE.PUB.SYS
```

SPUTIL

The Native Mode Spooler Utility Program (`SPUTIL`) allows you to list, manipulate, and transfer spooled device files (spoolfiles) that are created and maintained by MPE/iX. `SPUTIL` is an MPE/iX replacement for the MPE CM `SPOOK5` program.

`SPUTIL` opens the formal file designator `SPUTIN` as its `$$STDIN(X)` and the formal file designator `SPUTOUT` as its `$$STDLIST`. You may redirect these files as desired with a file equation. However the record width of any redirected `SPUTOUT` should not be less than 80 bytes; otherwise displays and messages may generate an error when `SPUTIL` directs them to `SPUTOUT`.

```
SPUTIL
```

STANDARDS

System bootstrap, initial program load (IPL), and initial system load (ISL) standard provides a standard interface through which any Hewlett-Packard Precision Architecture (PA-RISC) computer can boot any operating system. This standard also provides a common user interface for booting PA-RISC systems.

WARNING **The use of this information without service center support will void your warranty and may cause data loss.**

STORE/RESTORE

Use `STORE/RESTORE` to store and restore one or more files and directories to and from tape. Options let you store files for backup, transport, or archiving purposes.

```
STORE fileset [ ;parameters ]            RESTORE storfile [ ;parameters ]
```

SWITCH ASSIST TOOL

The Switch Assist Tool is an interactive utility that makes the job of creating an application with modules written both in native and compatibility modes easier to implement. Output is in the form of `PASCAL/iX` source code.

```
SWAT          or          RUN SWAT.PUB.SYS
```

SYSGEN

Use `SYSGEN` to modify your system configuration. Changes are written to disk or to tape. They do not become effective until the system is restarted. `SYSGEN` has a global module and four configurator modules:

1. Input/Output (I/O) Configurator. Configures local devices.
2. Logging (LOG) Configurator. Configures user and system logging processes.
3. Miscellaneous (MISC) Configurator. Configures miscellaneous items.
4. System File (SYSFILE) Configurator. Changes the list of files dumped to an SLT.

```
SYSGEN  
sysgen>command name
```

SYSMAP

`SYSMAP` displays the hardware configuration of a system by mapping I/O devices, CPU boards and memory boards. It displays device type, product number, logical device number (*ldev*) and device address. `SYSMAP` is part of the Online Diagnostics Subsystem. To use `SYSMAP`, first you enter `SYSDIAG` and get the Diagnostic User Interface prompt. Then you enter `RUN SYSMAP` and get `ENTER MAP>`, the `SYSMAP` prompt. Also see `IOMAP`.

```
SYSDIAG  
DUI> RUN SYSMAP  
ENTER MAP>
```

TERMDSM

Use the `TERMDSM` tool to diagnose, dump, and reset logical devices, ports, and data communications and terminal controllers (DTCs). `TERMDSM` also performs status checks of ports and DTC's.

```
SYSDIAG  
DUI > RUN TERMDSM
```

tic

The `tic` utility compiles source `terminfo` descriptions. The compiled entry is installed under the `/usr/lib/terminfo` directory hierarchy. If the `TERMINFO` environment variable is set, results are placed in the directory it points to instead. Entries are stored in directories that match the first character of their name. The entry for the VT-100 terminal, for example, is stored in `/usr/lib/terminfo/v/vt100`.

```
tic.hpbin.sys /product/curses/lib/terminfo/ansi
```

TTUTIL

TTUTIL is a screen-driven program that lets you modify characteristics of serial port connections (such as flow control, modem control, printer control and character handling) by modifying the terminal type file assigned to the port. You can create, modify or view an existing terminal or printer type file..

```
      RUN          OR          TTUTIL
TTUTIL.PUB.SYS
```

untic

The `untic` utility decompiles a `terminfo` binary file into its source format. If a `TERMINFO` environment variable is set, the `untic` utility searches the specified directory; otherwise, `untic` assumes the file is in the directory `/usr/lib/terminfo`. The output of an `untic` decompile is sent to the standard output

```
untic.hpbin.sys ansi
```

V7FF8CNV

In `VPLUS/XL` forms files, `V7FF8CNV` converts text and literals from a Hewlett-Packard 7-bit national substitution character set to `ROMAN8` character set.

```
V7FF8CNV          OR          RUN V7FF8CNV.PUB.SYS
```

VERSION

`VERSION` is a native mode utility program that displays program file information. For compatibility mode (CM) program files, it displays segment, stack, data reference base, and capabilities. For native mode (NM) executable files, it displays information on procedures, libraries, capabilities, stack, heap, entry names, and `$version` strings. (`$version` string information is displayed for NM object files and nonexecutable library files.) If `VERSION` is invoked without a file name or a file set for input, the `VERSION>` prompt continues until `EXIT` or a colon (`:`) is entered. If the input to `VERSION` is a file set, every file in the set will be processed even if an error occurs processing a previous file. If there is an error opening a file, the file system error will be displayed in addition to the `VERSION` error message.

```
or      VERSION          OR          VERSION filename
        VERSION "filename [ ,search string ]"
```

The *search string* is the name of a particular `$version` string in a system object module `SOM`. (Not applicable for CM program files.) The quotes are required if a search string is specified.

VOLUTIL

Use VOLUTIL commands to manipulate volume sets: to manage and maintain individual volumes, volume sets, and volume classes, and to make inquiries about their contents, availability, and status. You can use any MPE/iX system command from within VOLUTIL by entering a colon (:) before the command name. VOLUTIL commands are organized into four groups:

- Commands that operate on sets and end with 'SET' .
- Commands that deal with classes and end with 'CLASS' .
- Commands that control volumes and end with 'VOL' .
- Miscellaneous commands.

VOLUTIL
volutil> *command name*

OR

RUN VOLUTIL.PUB.SYS
volutil> *command name*

Utilities
Utilities Descriptions

3 Intrinsics Descriptions

Descriptions of the Intrinsics Available in MPE/iX

Alphabetical listing of all Intrinsics available.

ABORTSESS

NM and CM callable.

Enables a program to abort a specified job or session from the system.

```
          I16V I32V  I16A  
ABORTSESS(jsid,jsnum,jsstatus) ;
```

ACTIVATE

NM and CM callable.

Activates a newly created process, or a process suspended with the `SUSPEND` intrinsic. Requires process handling (PH) capability.

```
          I16V U16V  
ACTIVATE(pin,allow) ;
```

ADJUSTUSLF

NM and CM callable.

Adjusts directory space in a USL file by moving the start of the information block forward (or backward) on a user subprogram library (USL) file, thereby increasing (or decreasing) the space available for the file directory block. The overall length of the file does not change. This intrinsic is intended for programmers writing compilers. A USL contains CM object code and is meaningful only in the CM program development process.

```
          I16          I16V  I16V  
uslerror:=ADJUSTUSLF(uslfnnum,adjustment) ;
```

ALMANAC

NM and CM callable.

Returns the numeric date information for a date returned by the `CALENDAR` intrinsic. The returned information is year of century, month of year, day of month, and day of week.

```
          U16V  U16A          I16  I16          I16  I16  
ALMANAC(date,dterror, yearnum,monthnum,daynum,weekdaynum) ;
```

ALTDSEG

NM and CM callable.

Reduces the storage required by the extra data segment when moved into main memory and expands storage as required, allowing for a more efficient use of memory. Data segment management (DS) capability is required. Data segment management (DS) intrinsics are not recommended for use in the MPE/iX native mode programming environment; use of DS intrinsics degrade program performance.

```
U16V I16V I16  
ALTDSEG(index,increment,size);
```

ARITRAP

NM and CM callable.

Collectively enables all arithmetic traps (except the IEEE inexact result trap) or disables all arithmetic traps.

```
I*V  
ARITRAP(trapstate);
```

ASCII

NM and CM callable.

Converts a 16-bit binary number to a specified base and represents it as a numeric ASCII string.

```
I16 * I16V CA  
numchar:=ASCII(binvalue,base,asciieqv);
```

BEGINLOG

NM and CM callable.

Posts a special record to the user logging file to mark the beginning of a logical transaction. When BEGINLOG is called, the logging memory buffer is flushed to ensure that the record gets to the logging file. User logging (LG) or system supervisor (OP) capability is required.

```
I32 U16A I16 I16 I16  
BEGINLOG(index,data,length,mode,logstatus);
```

BINARY

NM and CM callable.

Converts a numeric (octal or decimal) ASCII string to a 16-bit twos complement binary value.

```
I16 CA I16V  
bineqv:=BINARY(asciieqv,length);
```

CALENDAR

NM and CM callable.

Returns the calendar date, including the day of year and the year of century.

```
U16  
date:=CALENDAR;
```

CATCLOSE

NM and CM callable.

Closes an application message catalog that was opened with CATOPEN.

```

          I32V      U16A
CATCLOSE ( catindex,catstatus )

```

CATOPEN

NM and CM callable.

Opens an application message catalog that was formatted with the GENCAT utility. CATOPEN returns a value that identifies the catalog and is used by CATREAD and CATCLOSE.

```

          I32      CA      U16A
catindex :=CATOPEN ( formaldesig,catstatus ) ;

```

CATREAD

NM and CM callable.

Provides access to messages in an application message facility formatted by the GENCAT utility. The CATOPEN intrinsic opens the message catalog.

```

          I16      I32V      I16V      I16V      U16A
msglength :=CATREAD ( catindex,setnum,msgnum,, catstatus ,
          CA      I16V      CA      CA      CA      CA      I16V
          buffer,bufferize,param1,param2,param3,param4,param5,msgdest ) ;

```

CAUSEBREAK

NM and CM callable.

Interrupts the program (the entire process structure). The CAUSEBREAK intrinsic is the programmatic equivalent to pressing **Break** in a session. It is not applicable in jobs. The program is suspended while in break mode. Execution of the program resumes where the interruption occurred if you enter the **RESUME** command, or aborts if you enter the **ABORT** command.

```

CAUSEBREAK ;

```

CLEANUSL

NM and CM callable.

Deletes all inactive entries from currently managed USL files and returns the file number of the new USL file. Therefore, you must test the condition code immediately upon return from the intrinsic. Unpredictable results occur if an error number is used as a file number. A USL contains CM object code and is meaningful in the CM program development process only.

```

          I16      I16V      CA
filenum :=CLEANUSL ( uslfnm,formaldesig ) ;

```

CLOCK

NM and CM callable.

Returns the time (hours, minutes, seconds, and tenths of seconds) according to the system timer.

```
I32
time :=CLOCK;
```

CLOSELOG

NM and CM callable.

Closes access to the user logging facility. User logging (LG) or system supervisor (OP) capabilities are required.

```
          I32  I16  I16
CLOSELOG ( index,mode,logstatus );
```

COMMAND

NM and CM callable.

Executes an MPE/iX command programmatically.

```
          CA      I16  I16
COMMAND ( cmdimage,cmderror,parmnum );
```

CREATE

NM and CM callable.

Creates a process as a child of the calling process. Process handling (PH) capability is required.

```
          CA          CA  I16 I16V U16V
CREATE ( formaldesig,entryname,pin,parm,loadflag,
          I16V I16V  I16V  U16V  I16V
          stacksize,dlsiz,maxdata,priorityclass,rank );
```

CREATEPROCESS

NM and CM callable.

Creates a process and allows you to assign \$STDIN and \$STDLIST to any file. Process handling (PH) capability is required.

```
          I*      I16  CA      I32A  I32A
CREATEPROCESS ( createstatus,pin,formaldesig,itemnum,item );
```

createstatus is a 32-bit signed integer by reference in Native Mode (NM), and a 16-bit signed integer by reference for Compatibility Mode (CM).

CTranslate

NM and CM callable.

Converts a string of characters between EBCDIC and ASCII, or between EBCDIK (HP-specific version of EBCDIC) and KANA8 (8-bit, Japanese International Standard (JIS) version of USASCII code).

```
          I16V      CA      CA      I16V      CA
CTranslate ( transcode,inbuffer,outbuffer,bufferlength, transtable );
```

DASCII

NM and CM callable.

Converts a 32-bit binary number to a specified base and represents it as a numeric ASCII string.

```
I16      I32V  I16V  CA
numchar := DASCII ( binvalue, base, asciieqv );
```

DATELINE

NM and CM callable.

Returns the current date and time, including the day of week, month, day, year, hours, and minutes.

```
CA
DATELINE ( datebuffer );
```

DBINARY

NM and CM callable.

Converts a numeric ASCII string to a 32-bit binary value. The numeric ASCII string can be octal, hexadecimal, or decimal.

```
I32      CA  I16V
dbineqv := DBINARY ( dasciieqv, length );
```

DEBUG

NM and CM callable.

Invokes the debug facility from an interactive program and allows object code to be analyzed. Consult the *MPE/iX System Debug Reference Manual (32650-90013)* before attempting to use the debug facility.

```
DEBUG;
```

DLSIZE

NM and CM callable.

Causes the area between DL and DB in the compatibility mode (CM) stack to be expanded or contracted within the CM stack segment.

```
I16      I16V
dlldsize := DLSIZE ( size );
```

DMOVIN

NM and CM callable.

Copies data from an extra data segment into a data area. Data segment management (DS) capability is required. Data segment management (DS) intrinsics are not recommended for use in the NM programming environment; use of DS intrinsics in NM degrades an NM program's performance.

```

      U16V      I16V      I16V      U16A
DMOVIN(index,displacement,number,location) ;
  
```

DMOVOUT

NM and CM callable.

Copies data from the data area to an extra data segment. Data segment management (DS) capability is required. Data segment management (DS) intrinsics are not recommended for use in the NM programming environment; use of DS intrinsics in NM degrades the NM program's performance.

```

      U16V      I16V      I16V      U16A
DMOVOUT(index,displacement,number,location) ;
  
```

ENDLOG

NM and CM callable.

Posts a record to the logging file marking the end of a logical transaction. When the record is posted, ENDLOG flushes the user logging memory buffer to ensure that the record gets to the logging file. User logging (LG) or system supervisor (OP) capability is required.

```

      I32  U16A  I16  I16  I16
ENDLOG(index,data,length,mode,logstatus) ;
  
```

EXPANDUSLF

NM and CM callable.

Changes length of a USL file by creating a USL file with the **increment** length longer or shorter than the USL file specified by **uslfnm**. The old USL file is copied to the new file with the same file name; the old USL file is then deleted. A USL contains CM object code and is meaningful only in the CM program development process.

```

      I16      I16V      I16V
filename := EXPANDUSLF(uslfnm,increment) ;
  
```

FATHER

NM and CM callable.

Returns the process identification number (PIN) of the parent calling process. Process handling (PH) capability is required.

```

      I16
pin := FATHER ;
  
```

FCHECK

NM and CM callable.

Returns specific details about error conditions that occurred when a file system intrinsic returns a condition code indicating an I/O error. FCHECK applies to files on any device.

```

      I16V      I16      I16      I32      I16
FCHECK(filename,fserrorcode,translog,blocknum,numrecs) ;
  
```

FCLOSE

NM and CM callable.

Terminates access to a file on any device by closing the reference file descriptor. If the file is not being accessed by another process, resources associated with the open file description are released.

```
FCLOSE(I16VfileI16Vnum,I16VdispoI16Vsition,I16VsecuI16Vritycode);
```

FCONTROL

NM and CM callable.

Performs various control operations on a file or on the device where the file resides, including:

- Supplying a printer or terminal carriage control directive.
- Verifying I/O.
- Reading the hardware status word for the device where the file resides.
- Setting a terminal's timeout interval.
- Repositioning a file at its beginning.
- Writing an end-of-file marker.
- Skipping forward or backward to a tape mark.

```
FCONTROL(I16VfileI16Vnum,I16Vitem*num,I16Vitem);
```

FDELETE

NM and CM callable.

Deactivates a specified logical record in an RIO file.

```
FDELETE(I16VfileI32Vnum,I32Vlrecnum);
```

FDEVICECONTROL

NM and CM callable.

Provides control operations to a printer, terminal, or a spooled device file and is used to:

- Download character sets, forms, and internal or control tables used in printing.
- Control the page size, pen positioning, form and use of character sets, the number of copies to be printed, and all other printing environment characteristics.
- Perform control operations on a terminal, printer, or spooled device file.

```
FDEVICECONTROL(I16VfileUDSnum,I16VbufI16Vfer,I16VlenI16Vgth,I16VconU16VtrolU16Vcode,U16VparmU16V1,U16VparmU16V2,U16VfsU16VerrorU16Vcode);
```

FERRMSG

NM and CM callable.

Returns a message corresponding to an FCHECK error number and enables error messages to be displayed from a program.

```
FERRMSG( I16 fserrorcode, CA msgbuffer, I16 msglength );
```

FFILEINFO

NM and CM callable.

Returns information about a file.

```
FFILEINFO( I16V filenum [ , I16V itemnum,item ] [ ... ] );
```

Up to five *itemnum/item* pairs can be specified.

FFINDBYKEY

NM and CM callable.

Positions the record pointer at the beginning of the first record matching the key value comparison. For KSAM files only.

```
FFINDBYKEY( I16V filenum, CA value, I16V location, I16V length, I16V relop );
```

FFINDN

NM and CM callable.

Positions the logical record pointer to the relative record number according to the key sequence. For KSAM files only.

```
FFINDN( I16V filenum, DV number, I16V location );
```

FGETINFO

NM and CM callable.

Returns access and status information about a file. FGETINFO is provided for compatibility with MPE V/E-based systems only. It is recommended that FFILEINFO be used to access data.

```
FGETINFO( I16V filenum, CA formaldesig, U16 foption, U16 aoption, I16 lrecsize, I16 devtype,  

U16 ldevnum, U16 hdaddr, I16 filecode, I32 lrecptr, I32 eof, I32 filelimit, I32 logcount, I32 physcount,  

I16 blksize, U16 extsize, I16 numextent, I16 userlabels, CA creatorid, I32 labaddr );
```

FGETKEYINFO

NM and CM callable.

Requests access and status information about a KSAM file. For KSAM files only.

```
FGETKEYINFO(I16V filenum,BA param,BA control)
```

FINDJCW

NM and CM callable.

Searches the job control word table for a specified job control word (JCW) and returns its value.

```
FINDJCW(CA jcwname,U16 jcwvalue,I16 jcwstatus);
```

FINTEXTIT

NM and CM callable.

Causes the return from your interrupt procedure.

```
FINTEXTIT(U16V interruptstate);
```

FINTSTATE

NM and CM callable.

Enables/disables all software interrupts against the calling process.

```
U16 oldstate := FINTSTATE(U16V interruptstate);
```

FLABELINFO

NM and CM callable.

Returns information from the file label of a disk file.

```
FLABELINFO(CA formal,I16V desig,I16 mode,I16A fserrorcode,REC itemnum,I16A item,I16A itemerror);
```

FLOCK

NM and CM callable.

Dynamically locks a file. If dynamically locking more than one RIN, multiple RIN (MR) capability is required.

```
FLOCK(I16V filenum,U16V lockflag);
```

FLUSHLOG

NM and CM callable.

Flushes the contents of the user logging memory buffer to the user logging file. User logging (LG) or system supervisor (OP) capability is required.

```
          I32  I16  
FLUSHLOG(index,logstatus);
```

FMTCALENDAR

NM and CM callable.

Passes any calendar date, in the same format as the CALENDAR intrinsic, and returns it in the following format: FRI, JAN 27, 1989

```
          U16V  CA  
FMTCALENDAR(date,formatdate);
```

FMTCLOCK

NM and CM callable.

Passes the time of day, in the same format as the CLOCK intrinsic, and returns it in the following format:

```
12:39 AM  
  
          I32V  CA  
FMTCLOCK(time,formattime);
```

FMTDATE

NM and CM callable.

Passes in the calendar date and time of day, in the same format as the CALENDAR and CLOCK intrinsics, and returns it in the following format:

```
FRI, JAN 27, 1989, 12:39 AM  
  
          U16V I32V  CA  
FMTDATE(date,time,datetime);
```

FOPEN

NM and CM callable.

Establishes access to a file and defines the physical characteristics of the file prior to access.

```
          I16          CA  U16V  U16V  I16V  CA  CA  I16V  
filenum:=FOPEN(formaldesig,foption,aoption,resize,device,formmsg,userlabels,  
              I16V  I16V  I32V  I16V  I16V  I16V  
              blockfactor,numbuffer,filesize,numextent,initialloc,filecode);
```

FPARSE

NM and CM callable.

Parses and validates MPE (only) file designators.

```
          CA  I16A U16A I32A  
FPARSE(formaldesig,result,item,vector);
```

FPOINT

NM and CM callable.

Sets the logical record pointer for a disk file containing fixed-length or undefined-length records to any logical record. When the next FREAD or FWRITE file request is made, this record is read or written to.

(KSAM) Sets both the chronological and logical record pointers to the next record in chronological sequence (the order records were written to the file).

```
          I16V    I32V
FPOINT( filenum,lrecnum );
```

FREAD

NM and CM callable.

Reads a logical record or portion of a record from a file to the stack.

```
          I16          I16V  UDS    I16V
transfercount := FREAD( filenum,buffer,length );
```

FREADBACKWARD

NM and CM callable.

Reads a logical record backward from the current record pointer. Data is presented as if read forward. Used for tape files only. Can recover tape errors when handling I/O management and data recovery routines.

```
          I16          I16V  UDS    I16V
transfercount := FREADBACKWARD( filenum,buffer,length );
```

FREADBYKEY

NM and CM callable.

Reads a logical record randomly from a KSAM file to the data stack. For KSAM file only.

```
          I16V          I16V  LA    I16V  CA    I16V
length := FREADBYKEY( filenum,target,tcount,value,location );
```

FREADC

NM and CM callable.

Reads a logical record in chronological sequence from a KSAM file to the data stack. For KSAM files only.

```
          I16V          I16V  LA    I16V
length := FREADC( filenum,target,tcount );
```

FREADDIR

NM and CM callable.

Reads a specific logical record or portion of a record from a direct-access disk file to the data stack.

```
      I16V  UDS  I16V  I32V  
FREADDIR(filenum,buffer,length,lrecnum) ;
```

FREADLABEL

NM and CM callable.

Reads a user-defined label from a disk or magnetic tape file.

```
      I16V  UDS  I16V  I16V  
FREADLABEL(filenum,buffer ,length,labelid) ;
```

FREADSEEK

NM and CM callable.

Moves a record from a disk file to a buffer in anticipation of a FREADDIR intrinsic call.

```
      I16V  I32V  
FREADSEEK(filenum,lrecnum) ;
```

FREEDSEG

NM and CM callable.

Releases an extra data segment assigned it by the GETDSEG intrinsic. Data segment management (DS) capability is required. Data segment management (DS) intrinsics are not recommended for use in the MPE/iX native mode programming environment. Use of DS intrinsics in NM will degrade your program's performance.

```
      U16V U16V  
FREEDSEG(index,id) ;
```

FREELOCRIN

NM and CM callable.

Frees all local resource identification numbers (RINs) from allocation to a job/session.

```
FREELOCRIN ;
```

FRELATE

NM and CM callable.

Determines whether a file pair (on any device) is interactive, duplicative, or both interactive and duplicative.

```
      U16          I16V  I16V  
intordup := FRELATE(infilenum,listfilenum) ;
```

FREMOVE

NM and CM callable.

Marks the current record in a KSAM file for deletion. For KSAM files only.

```
      I16V  
FREMOVE(filenum)
```

FRENAME

NM and CM callable.

Renames an open disk file (and its lockword, if applicable). The file being renamed must be either:

- A new file.
- An old file (permanent or temporary), opened for exclusive access with the *exclusive* option of the HPFOPEN/FOPEN intrinsics, and with security provisions allowing write access.

```
FRENAME ( I16Vfilenum, CAformalCAdesig ) ;
```

FSETMODE

NM and CM callable.

Controls the following access modes of files or devices:

- Issuing carriage return and line feed to terminal after a terminal read.
- Reporting tape automatic error recovery.
- Guaranteeing chronological order of user program write requests.
- Blocking program execution until physical completion of write requests.

```
FSETMODE ( I16Vfilenum, U16Vmodeflags ) ;
```

FSPACE

NM and CM callable.

Moves a record pointer forward or backward on a magnetic tape or disk file, spaces physical records on magnetic tape files and logical records on disk files.

```
FSPACE ( I16Vfilenum, I16Vdisplacement ) ;
```

FUNLOCK

NM and CM callable.

Dynamically unlocks a file's global resource identification number (RIN) that was locked with the FLOCK intrinsic.

```
FUNLOCK ( I16Vfilenum ) ;
```

FUPDATE

NM and CM callable.

Updates (writes) a logical record in a disk file.

```

      I16V  UDS  I16V
FUPDATE( filenum,buffer,length );

```

FWRITE

NM and CM callable.

Writes a logical or physical record or portion of a record from the stack to a file on any device.

```

      I16V  UDS  I16V  U16V
FWRITE( filenum,buffer,length,controlcode );

```

FWRITEDIR

NM and CM callable.

Writes a specific logical record from the stack to a disk file.

```

      I16V  UDS  I16V  I32V
FWRITEDIR( filenum,buffer,length,lrecnum );

```

FWRITELABEL

NM and CM callable.

Writes a user-defined label onto a disk file or magnetic tape file that is labeled with an ANSI-standard or IBM-standard label. It also overwrites old user labels.

```

      I16V  UDS  I16V  I16V
FWRITELABEL( filenum,buffer, length,labelid );

```

GENMESSAGE

NM and CM callable.

Provides access to messages in catalogs that were formatted with the MAKECAT utility.

```

      I16      I16V  I16V  I16V  CA  I16V  I16V
msglength := GENMESSAGE( filenum,setnum,msgnum, buffer,buffer,buffer,buffer,
      *      *      *      *      *      I16V      I16
      param1,param2,param3,param4,param5,msgdestination,errornum );

```

GETDSEG

NM and CM callable.

Creates or acquires an extra data segment for use by the process. Data segment management (DS) capability is required. Data segment management (DS) intrinsics are not recommended for use in the MPE/iX native mode programming environment. Use of DS intrinsics in NM degrades your program's performance.

```

      U16  I16  U16V
GETDSEG( index,length,id );

```

GETINFO

NM and CM callable.

Returns user-supplied information that was passed to a process when it was created.

```

I16      CA      I16      I16
result := GETINFO( infostring, infostringlength, parm );

```

GETJCW

NM and CM callable.

Returns the value of the system-defined job control word (JCW) to the calling process.

```

U16
jcw := GETJCW;

```

GETLOCRIN

NM and CM callable.

Acquires local resource identification numbers (RINs) for a job/session.

```

U16V
GETLOCRIN( rincount );

```

GETORIGIN

NM and CM callable.

Returns the source of the activation call for the calling process that has been previously suspended and subsequently reactivated. The source of the activation request can be the parent process, a child process, or another source (for example, an interrupt or the timer). Process handling (PH) capability is required.

```

I16
source := GETORIGIN;

```

GETPRIORITY

NM and CM callable.

Changes the priority of a process. Process handling (PH) capability is required.

```

I16V      U16V      I16V
GETPRIORITY( pin, priorityclass, rank );

```

GETRIVMODE

NM and CM callable.

Dynamically enters privileged mode. Privileged mode (PM) capability is required. The normal checks and limitations that apply to the standard users in MPE/iX are bypassed in privileged mode (PM). It is possible for a PM program to destroy file integrity, including the MPE/iX operating system software itself. Hewlett-Packard will investigate and attempt to resolve problems resulting from the use of PM code. This service, which is not provided under the standard service contract, is available on a time and materials billing basis. Hewlett-Packard will not support, correct, or attend to any modification of the MPE operating system software.

```

GETRIVMODE;

```

GETPROCID

NM and CM callable.

Returns the process identification number (PIN) of a child process. Process handling (PH) capability is required.

```
I16          I16V  
pin := GETPROCID(numchild) ;
```

GETPROCINFO

NM and CM callable.

Returns status information about the parent or a child process. Process handling (PH) capability is required.

```
I32          I16V  
processinfo := GETPROCINFO(pin) ;
```

GETUSERMODE

NM and CM callable.

Dynamically returns a program to nonprivileged mode.

```
GETUSERMODE ;
```

HP32208

CM callable only.

Returns the current VUF (version, update, fix level) of KSAM/3000.

```
D  
version := HP32208
```

HPACDINFO

Lists security information from the access control definition (ACD) of a specified file or device. Any user with RACD access to an ACD can obtain information about that ACD.

Syntax

```
I32 IV * HPACDINFO(status,itemnum1,item1 IV * [,itemnum2,item2][,...]);
```

HPACDPUT

Manipulates security information in the access control definition (ACD) of a specified file or device.

Syntax

```
I32 IV * IV * HPACDPUT(status,itemnum1,item1,itemnum2,item2);
```

HPCICOMMAND

NM callable only.

Executes a command programmatically.

```
HPCICOMMAND(CA cmdimage,I16 cmderror ,I16 parmnum,I16V msglevel) ;
```

HPCIDELETEVAR

NM callable only.

Removes a valid variable name from the session-level variable table.

```
HPCIDELETEVAR(CA varname ,I32 status) ;
```

HPCIGETVAR

NM callable only.

Retrieves a valid variable name from the session-level variable table and returns the current value and/or attributes.

```
HPCIGETVAR(CA varname ,I32 status [ ,U32 itemnum,* item] [ . . . ])
```

Up to six *itemnum/item* pairs can be specified.

HPCIPUTVAR

NM callable only.

Sets the value of a session-level variable.

```
HPCIPUTVAR(CA varname ,I32 status [ ,U32 itemnum,* item] [ . . . ])
```

Up to three *itemnum/item* pairs can be specified.

HPDEBUG

NM callable only.

Enters the system debugger and optionally executes a defined set of system debug commands.

```
HPDEBUG(I32 status,CA cmdstr [ ,I32V itemnum,* item] [ . . . ] ) ;
```

HPDEVCONTROL

NM callable only.

Provides access to specified peripheral functionality without the device being opened. Allows access to device utilities; not for general control (for example, reading or writing). Nonshareable device (ND) capability is required.

```
          I32  CA    I32  I32  
HPDEVCONTROL ( status, ldev, itemnum , item ) ;
```

HPENBLTRAP

NM callable only.

Selectively enables or disables arithmetic traps.

```
          I32V  I32  
HPENBLTRAP ( mask, oldmask ) ;
```

HPERRDEPTH

NM callable only.

Returns the current depth of the process error stack.

```
          I32  I32  
HPERRDEPTH ( depth , status ) ;
```

HPERRMSG

NM callable only.

Obtains or displays error messages from the system catalog.

```
          I32V  I32V  I16    I32V  CA    I16  I32  
HPERRMSG ( displaycode , depth, errorproc, errornum, buffer, buflength, status ) ;
```

HPERRREAD

NM callable only.

Reads any specified error from the process stack.

```
          I32V  I32    I32  I32  
HPERRREAD ( depth, errornum , procnum, status )
```

HPFDUPLICATE

NM callable only.

Creates duplicate file descriptors for files opened for MULTI, SHARED, or EXCLUSIVE access.

Syntax

```
          I16          I32  I32V  
*filenum : =HPFDUPLICATE ( source , status , target ) ;
```

HPFIRSTLIBRARY

NM callable only.

Returns the file name of the first native mode executable library (XL) in the binding sequence of the calling process.

```

      CA      I32  I32
HPFIRSLIBRARY ( formaldesig, status, length ) ;

```

HPFOPEN

NM callable only.

Establishes access to a file on any device and creates a file on any shareable device.

```

      I32      I32      I32V      *
HPFOPEN ( filenum, status [ , itemnum, item ] [ . . . ] ) ;

```

Up to 41 *itemnum/item* pairs can be specified.

HPFPCONVERT

NM callable only.

Converts data between binary floating-point formats.

```

      *      *      I16V      I16V      I32      I16      I16V
HPFPCONVERT ( source, destination, sformat, dformat, status, exceptions, roundmode )

```

HPGETPROCPLABEL

NM callable only.

Dynamically loads a native mode (NM) executable library procedure.

```

      CA      U32      I32      CA      B
HPGETPROCPLABEL ( procname, label, status, firstfile, casesensitive ) ;

```

HPLOADCMPROCEDURE

NM callable only.

Obtains CM procedure label in preparation for Switch to CM through label.

```

      U16      CA      U16V      I32
plabel := HPLOADCMPROCEDURE ( procname, library, status ) ;

```

HPLOADNMPROC

CM callable only.

Returns the label of an NM procedure.

```

      U32      CA      I16V      CA      I16V
plabel := HPLOADNMPROC ( procname, proclen, libname, liblen ) ;

```

HPMERGEEND

NM callable only.

Releases the MERGE/XL work area and ends the merging operation.

```

      I32      I32A
HPMERGEEND ( status, statistics ) ;

```

HPMERGEERRORMESS

NM callable only.

Accepts HP MERGE intrinsic error code values and returns the error messages associated with them.

```
          I32   CA   I32  
HPMERGEERRORMESS ( status,message,length ) ;
```

HPMERGEINIT

NM callable only.

Initializes the MERGE/XL subsystem.

```
          I32   I32A   PROC   I32A   PROC  
HPMERGEINIT ( status,inputfiles,preprocessor,outputfiles,postprocessor,  
          32V   I32V I32A CA   PROC   PROC   I32A   I32V   I32A  
keyonly,numkeys,keys,altseq,keycompare,errorproc,statistics,memsize,charseq ) ;
```

HPMERGEOUTPUT

NM callable only.

Retrieves records, one at a time, from MERGE/XL.

```
          I32   CA   I32  
HPMERGEOUTPUT ( status,buffer,length ) ;
```

HPMERGESTAT

NM callable only.

Prints MERGE/XL statistics on \$STDLIST.

```
          I32   I32A  
HPMERGESTAT ( status,statistics ) ;
```

HPMERGETITLE

NM callable only.

Prints the version number and title information for MERGE/XL on \$STDLIST.

```
          I32  
HPMERGETITLE ( status ) ;
```

HPMYFILE

NM callable only.

Returns the file name of the native mode program or executable library (XL) that called the HPMYFILE intrinsic.

```
          CA   I32 I32  
HPMYFILE ( formaldesig, status,length ) ;
```

HPMYPROGRAM

NM callable only.

Returns the file name of the program being executed by the calling process.

```
HPMYPROGRAM(CA formalI32 desigI32, status, length);
```

HPRESETDUMP

NM callable only.

Disarms the system debugger call from a process abort.

```
HPRESETDUMP(I32 status);
```

HPSETCCODE

NM callable only.

Sets the condition code for the calling process.

```
HPSETCCODE(I32V ccodevalue);
```

HPSETDUMP

NM callable only.

Arms the system debugger call from a process abort.

```
HPSETDUMP(I32 status, CA cmdstr);
```

HPSORTEND

NM callable only.

Releases the SORT/XL work area and ends the sorting operation.

```
HPSORTEND(I32 status, I32A statistics);
```

HPSORTERRORMESS

NM callable only.

Retrieves an error message if a fatal error occurs in SORT/XL.

```
HPSORTERRORMESS(I32 status, CA message, I32 length);
```

HPSORTINIT

NM callable only.

Initializes the SORT/XL subsystem.

```

      I32  I32A  I32A  I32  I32V  I32V  I32V
HPSORTINIT ( status,inputfiles,outputfiles,outputoption,reclength,numrecs,numkeys,
      I32A CA  PROC  PROC  I32A  I32V  I32A
      keys,altseq,keycompare,errorproc,statistics,memsize,charsseq ) ;
  
```

HPSORTINPUT

NM callable only.

Passes records, one at a time, to SORT/XL.

```

      I32  CA  I32V
HPSORTINPUT ( status,buffer,length ) ;
  
```

HPSORTOUTPUT

NM callable only.

Retrieves records, one at a time, from SORT/XL program.

```

      I32  CA  I32
HPSORTOUTPUT ( status,buffer,length ) ;
  
```

HPSORTSTAT

NM callable only.

Prints the SORT/XL statistics on \$STDLIST.

```

      I32  I32A
HPSORTSTAT ( status,statistics ) ;
  
```

HPSORTTITLE

NM callable only.

Prints the version number and title information for SORT/XL on \$STDLIST and prints the date and time produced by the DATELINE intrinsic.

```

      I32
HPSORTTITLE ( status ) ;
  
```

HPSWITCHTOCM

NM callable only.

Makes native mode (NM) to compatibility mode (CM) mixed-mode procedure calls possible.

```

      REC  I32V  I32V  RECA  I32V  RECV  I16  I32
HPSWITCHTOCM ( proc,method,numparms,parms ,fretlen,fretval,condcode,status ) ;
  
```

HPSWTONMNAME

CM callable only.

Allows CM user programs, user libraries, and system code to invoke NM procedures as follows:

- Convert CM references in an argument list to virtual NM addresses.

- Change the execution mode.
- Invoke the NM procedure specified by the CM caller.

```
HPSWTONMNAME ( CA I16V CA I16V I16V I16 I16 I16V
                ( procname,proclen,libname,liblen,nparms,arglist,argdesc,functype ) ;
```

HPSWTONMPLABEL

CM callable only.

Allows CM user programs, user libraries, and system code to invoke NM procedures as follows:

- Convert CM references in the argument list to virtual NM addresses.
- Change the execution mode.
- Invoke the NM procedure specified by the CM caller.

```
HPSWTONMPLABEL ( U32V I16V I16 I16 I16V
                 ( proc,nparms,arglist,argdesc,functype ) ;
```

HPUNLOADCMPROCEDURE

NM callable only.

Unloads a target CM procedure whose plabel is obtained through the HPLOADCMPROCEDURE intrinsic.

```
HPUNLOADCMPROCEDURE ( CA U8V I32
                      ( procname,library , status ) ;
```

INITUSLF

NM and CM callable.

Initializes a USL file to the empty state. A USL contains CM object code and is meaningful only in the CM program development process.

```
I16 I16V I16A
uslerror := INITUSLF ( uslfnnum,record ) ;
```

IODONTWAIT

NM and CM callable.

Initiates completion operations for an I/O request.

```
I16 I16V UDS I16 U16
fnum := IODONTWAIT ( filenum , buffer,length,cstation )
```

IOWAIT

NM and CM callable.

Initiates completion operations for an I/O request.

```
I16 I16V UDS I16 U16
fnum := IOWAIT ( filenum,buffer,length,cstation ) ;
```

JOBINFO

NM and CM callable.

Provides access to job and session information.

```
      I16V  I32    U16A      I16V   *    I16  
JOBINFO(jsind,jsnum,jsstatus) [ , itemnum,item,itemerror] [ . . . ] ;
```

Up to five *itemnum/item/itemerror* triples can be specified.

KILL

NM and CM callable.

Deletes a child process of the calling process and all of its descendants. Process handling (PH) capability is required.

```
      I16V  
KILL(pin) ;
```

LOADPROC

NM and CM callable.

Dynamically loads a compatibility mode (CM) segmented library (SL) procedure and any external procedures it has referenced.

```
      I16          CA      I16V  I16  
idnum := LOADPROC(procname,library,label) ;
```

LOCKGLORIN

NM and CM callable.

Locks a global resource identification number (RIN). Multiple RIN (MR) capability is required to lock more than one global RIN simultaneously.

```
      I16V      U16      CA  
LOCKGLORIN(rinum,lockflag,rinpassword) ;
```

LOCKLOCRIN

NM and CM callable.

Locks a local resource identification number (RIN).

```
      I16V      U16  
LOCKLOCRIN(rinum,lockflag) ;
```

LOCRINOWNER

NM and CM callable.

Determines process identification number (PIN) of the process that locked a local resource identification number (RIN).

```
      I16          I16V  
pin := LOCRINOWNER(rinum) ;
```

LOGINFO

NM and CM callable.

Provides information about an opened user logging file (whole file set). User logging (LG) or system supervisor (OP) capability is required.

```
LOGINFO ( I32V index, I16 logstatus [ , I16V itemnum, * item ] [ . . . ] ) ;
```

Up to four *itemnum/item* pairs can be specified.

LOGSTATUS

NM and CM callable.

Provides information about a currently opened user logging file. User logging (LG) or system supervisor (OP) capability is required.

```
LOGSTATUS ( I32 index, U16A loginfo, I16 logstatus ) ;
```

MAIL

NM and CM callable.

Determines the status of the mailbox used by its parent or child. Process handling (PH) capability is required.

```
U16 mailstatus := MAIL ( I16V pin, I16 length ) ;
```

MERGEEND

NM and CM callable.

Restores the data stack to its original state and ends the merging operation.

```
MERGEEND ;
```

MERGEERRORMESS

NM and CM callable.

Retrieves a message if a fatal error occurs during the MERGE/XL operation and converts MERGEINIT error code values into ASCII strings.

```
MERGEERRORMESS ( I16V errorcode, CA message, I16 length ) ;
```

MERGEINIT

NM and CM callable.

Initializes the MERGE/XL subsystem and the merging of two or more sorted files.

```
MERGEINIT ( I16A inputfiles, PROC preprocessor, I16A outputfiles, PROC postprocessor, I16V keysonly, I16V numkeys,  
I16A keys, I16A altseq, PROC keycompare, PROC errorproc, I16A statistics, I16 failure, I16 errorparm, I16 spaceallocation, I16A charseq ) ;
```

MERGEOUTPUT

NM and CM callable.

Provides an alternative method of specifying how records are output from the MERGE program.

```
          CA   I16  
MERGEOUTPUT ( record,length ) ;
```

MERGESTAT

NM and CM callable.

Prints the MERGE program statistics on \$STDLIST.

```
          I16A  
MERGESTAT ( statistics ) ;
```

MERGETITLE

NM and CM callable.

Prints the version number and title of the merge segment on \$STDLIST and prints the date and time produced by the DATELINE intrinsic.

```
MERGETITLE ;
```

MYCOMMAND

NM and CM callable.

Parses (delineates and defines) parameters for a user-defined command image.

```
          I16          CA          CA          I16V          I16          I32A  
entrynum : =MYCOMMAND ( cmdimage , delimiters , maxparms,numparms,params ,  
          CA          @*  
          dictionary,definition ) ;
```

NLAPPEND

NM and CM callable.

Appends a language ID number to a file name that allows an application to designate which language-dependent file to use.

```
          CA          I16V          U16A  
NLAPPEND ( formaldesig,langnum,error ) ;
```

NLCOLLATE

NM and CM callable.

Collates two character strings according to the specified language collating sequence and determines a lexical ordering.

```
          CA          CA          I16V          I16          I16V          U16A          U16A  
NLCOLLATE ( buffer1,buffer2,bufferlength,result,langnum,error , collseq ) ;
```

NLCONVCLOCK

NM and CM callable.

Converts the time format from a character string to numeric value; checks the input string using the formatting template returned by *itemnum*=3 of the NLINFO intrinsic, then converts the time to the general time format returned by the CLOCK intrinsic.

```
I32          CA      I16V      I16V  U16A
time := NLCONVCLOCK ( buffer,bufferlength,langnum,error ) ;
```

NLCONVCUSTDATE

NM and CM callable.

Converts the custom date format from a character string to a numeric value; checks the input string by using the formatting template returned by item 2 of the NLINFO intrinsic, then converts the date to the general date format as returned by the CALENDAR intrinsic.

```
U16          CA      I16V      I16V  U16A
date := NLCONVCUSTDATE ( buffer,bufferlength,langnum,error ) ;
```

NLCONVNUM

NM and CM callable.

Converts native language numbers with native decimal and thousands separators to an ASCII number with NATIVE-3000 decimal and thousands separators. Optionally, the decimal and thousands separators can be removed.

```
          I16V  CA      I16V      CA      I16V  U16V
NLCONVNUM( langnum,instring,length1,outstring,outlength,error ,
          U16V  U16V      U16V      O-V
          numspec,fmtmask,decimals ) ;
```

NLFINDSTR

NM and CM callable.

Searches **string1** for **string2**, and returns an integer value indicating the offset in **string1** where **string2** was found.

```
I16          I16V  CA      I16V      CA      I16V  U16A  U16A
offset := NLFINDSTR ( langnum,string1,length1,string2,length2,error , charset ) ;
```

NLFMTCALENDAR

NM and CM callable.

Formats the date according to language-dependent templates. The formatting is done according to the template returned by *itemnum*= 1 of the NLINFO intrinsic.

```
          U16V  CA      I16V  U16A
NLFMTCALENDAR ( date,buffer,langnum,error ) ;
```

NLFMTCLOCK

NM and CM callable.

Formats the time of day, in the specified language, obtained with the `CLOCK` intrinsic.

```

      I32V  CA  I16V  U16A
NLFMTCLOCK( time,buffer,langnum,error );
  
```

NLFMTCUSTDATE

NM and CM callable.

Formats the general date format returned by the `CALENDAR` intrinsic into the custom date format for a native language. A custom date is an abbreviated format such as 10/1/82 or 82.10.1. The formatting is done according to the template returned by `itemnum=2` of the `NLINFO` intrinsic.

```

      U16V  CA  I16V  U16A
NLFMTCUSTDATE( date,buffer,langnum,error );
  
```

NLFMTDATE

NM and CM callable.

Formats the date and time according to language-dependent templates returned by `itemnums 1` and `3` of the `NLINFO` intrinsic.

```

      U16V I32V  CA  I16V  U16A
NLFMTDATE( date,time,buffer,langnum,error );
  
```

NLFMTLONGCAL

NM and CM callable.

Formats the supplied date according to the long calendar format. The formatting is done according to the template returned by `NLINFO itemnum=30`.

```

      LV  BA  IV  LA
NLFMTLONGCAL( date,string,langnum,error );
  
```

NLFMTNUM

NM and CM callable.

Converts a string containing an ASCII number (can include `NATIVE-3000` decimal separator (`.`), thousands separator (`,`), and currency symbol/name (`$`)) to a language-specific format using the decimal separator, thousands separator, and currency symbol/name defined for the native language.

```

      I16V  CA  I16V  CA  I16V  U16A
NLFMTNUM( langnum,instring,inlength,outstring,outlength,error ,
      U16A  U16V  I16V  O-V
      numspec,fmtmask,decimals )
  
```

NLGETLANG

NM and CM callable.

Returns a language ID number that characterizes the current user, data, or system. Hewlett-Packard subsystems and application programs use `NLGETLANG` for automatic configuration.

```

      I16          I16V      U16A
langnum := NLGETLANG ( langtype, error );

```

NLINFO

NM and CM callable.

Returns language-dependent information. The type of information that can be obtained includes:

- Calendar format
- Date and time format
- Currency
- Collating
- Translation
- Character set

```

      I16V      *      I16      U16A
NLINFO ( itemnum, item, langnum, error );

```

NLJUDGE

NM and CM callable.

Judges whether a character is a 1 byte or 2 byte Asian character.

```

      I16V          I16V      CA      I16V      CA      U16A      U16A
n2bytes := NLJUDGE ( langnum, instring, stringlength, flags, error, charset );

```

NLKEYCOMPARE

NM and CM callable.

Compares two strings of different length (for use with KSAM generic key searching).

```

      CA      I16V      CA      I16V      I16      I16V      U16A      U16A
NLKEYCOMPARE ( generickey, length1, key, length2, result, langnum, error, collseq );

```

NLNUMSPEC

NM and CM callable.

Returns the information needed for formatting and converting numbers. It combines several calls to NLINFO to simplify the use of native language formatting. By calling NLNUMSPEC once, and passing the obtained information to NLFMTNUM and NLCONVNUM, implicit calls to NLNUMSPEC from NLFMTNUM and NLCONVNUM are avoided and performance is improved.

```

      I16V      U16A      U16A
NLNUMSPEC ( langnum, string, error );

```

NLREPCHAR

NM and CM callable.

Replaces all nondisplayable control characters in the string with the replacement character. Nondisplayable characters are those with attribute 3 (undefined graphic character) or 5 (control code), as returned by *itemnum=12* of the NLINFO intrinsic.

```
NLREPCCAHACAR(I16V inbuffer,CV outbuffer,I16V bufferlength,I16V replacechar,U16A langnum,U16A error , charset) ;
```

NLSCANMOVE

NM and CM callable.

Scans and moves character strings according to character attributes. This function is handled in a language-dependent manner.

```
numchar:I16 =NLSCANMOVE(CA inbuffer,CA outbuffer,U16V flags,I16V bufferlength,I16V langnum,I16V error ,U16A charset,CA shiftinfo) ;
```

NLSUBSTR

NM and CM callable.

Extracts **movelength** bytes from the **instring** to the **outstring**.

```
NLSUBSTR(CA instring,I16V inlength,CA outstring,I16 outlength,I16V startposition,16V movelength,I16V langnum,I16V flags,U16A error , charset) ;
```

NLSWITCHBUF

NM and CM callable.

Converts a string of characters from phonetic order to screen order or from screen order to phonetic order.

```
NLSWITCHBUF(I16V langnum,CA instring,CA outstring,I16V stringlength,U16V left-to-right,U16A error) ;
```

NLTRANSLATE

NM and CM callable.

Translates a string of characters from EBCDIC-to-ASCII or ASCII-to-EBCDIC using the appropriate native language table.

```
NLTRANSLATE(I16V transcode,CA inbuffer,CA outbuffer,I16V bufferlength,I16V langnum,U16A error ,  

transtable) ;
```

OPENLOG

NM and CM callable.

Provides access to the user logging facility. User logging (LG) or system supervisor (OP) capability is required.

```

      I32  CA  CA  I16  I16
OPENLOG(index,logid,pass,mode,logstatus);

```

PAUSE

NM and CM callable.

Suspends the calling process for a specified number of seconds.

```

      32R
PAUSE(interval);

```

PRINT

NM and CM callable.

Prints character string on job/session listing device.

```

      CA  I16V  I16V
PRINT(message,length,controlcode);

```

PRINTFILEINFO

NM and CM callable.

Prints a file or directory information display on the job/session list device.

```

      I16V
PRINTFILEINFO(filenum);

```

PRINTOP

NM and CM callable.

Prints a character string on the system console.

```

      CA  I16V  I16V
PRINTOP(message,length,controlcode);

```

PRINTOPREPLY

NM and CM callable.

Prints a character string on the system console and solicits a reply.

```

      I16  CA  I16V  I16V  CA  I16V
length:=PRINTOPREPLY(message,length,zero,reply,maxlength);

```

PROCINFO

NM and CM callable.

Provides access to process information.

```

      I16  I16  I16V  I16V  *
PROCINFO(error1,error2,pin[ ,itemnum,item] [ . . . ]);

```

Up to six *itemnum/item* pairs can be specified.

PROCTIME

NM and CM callable.

Returns the accumulated CPU time for a process.

```
      I32  
time := PROCTIME ;
```

PUTJCW

NM and CM callable.

Assigns the value of a particular job control word (JCW) in the job control word table.

```
      CA      U16      I16  
PUTJCW(jcwname, jcwvalue, jcwstatus) ;
```

QUIT

NM and CM callable.

Aborts the calling process.

```
      I16V  
QUIT(num) ;
```

QUITPROG

NM and CM callable.

Aborts the entire user process structure.

```
      I16V  
QUITPROG(num) ;
```

READ

NM and CM callable.

Reads an ASCII string from \$STDIN into an array.

```
      I16      CA      I16V  
length := READ(message, msglength) ;
```

READX

NM and CM callable.

Reads an ASCII string from \$STDINX into an array.

```
      I16      CA      I16V  
length := READX(message, msglength) ;
```

RECEIVEMAIL

NM and CM callable.

Receives mail from another process. Process handling (PH) capability is required.

```

U16          I16V UDS          U16V
mailstatus := RECEIVEMAIL ( pin, location, waitflag );

```

RESETCONTROL

NM and CM callable.

Reenables the subsystem break trap which allows a process to accept other subsystem break signals.

```
RESETCONTROL;
```

RESETDUMP

NM and CM callable.

Disables the abort stack analysis facility. Only the current process is affected.

```
RESETDUMP;
```

SEARCH

NM and CM callable.

Searches a specially-formatted array for a specified entry or name.

```

I16          CA I16V          CA          @*
entrynum := SEARCH ( buffer, length, dictionary, definition );

```

SENDMAIL

NM and CM callable.

Sends mail to another process. Process handling (PH) capability is required.

```

U16          I16V I16V          UDS          U16V
mailstatus := SENDMAIL ( pin, length, location, waitflag );

```

SETDUMP

NM and CM callable.

Arms a call to the system debugger from a process abort.

```

I16V
SETDUMP ( flags );

```

SETJCW

NM and CM callable.

Sets bits in the system job control word (JCW).

```

U16V
SETJCW ( jcwword );

```

SORTEND

NM and CM callable.

Closes the scratch file and restores the data stack to its original state.

```
SORTEND ;
```

SORTERRORMESS

NM and CM callable.

Retrieves and prints a message if a fatal error occurs during the SORT program.

```
                I16V   CA   I16  
SORTERRORMESS ( errorcode,message,length ) ;
```

SORTINIT

NM and CM callable.

Initiates the SORT program.

```
                I16A   I16A   I16V   I16V   I32V   I16V   I16A  
SORTINIT( inputfiles,outputfiles,outputoption,reclength,numrecs,numkeys,keys ,  
          I16A   PROC   PROC   I16A   I16   I16   I16   I16A  
altseq,keycompare,errorproc,statistics,failure,errorparm,spaceallocation,charseq ) ;
```

SORTINPUT

NM and CM callable.

Provides an alternative method of specifying how records are supplied to the SORT program.

```
                CA   I16V  
SORTINPUT( record,length ) ;
```

SORTOUTPUT

NM and CM callable.

Provides an alternative method of specifying how records are output from the SORT program.

```
                CA   I16  
SORTOUTPUT( record,length ) ;
```

SORTSTAT

NM and CM callable.

Prints the SORT program statistics on \$STDLIST. Call SORTSTAT after you have called the SORTEND intrinsic.

```
                I16A  
SORTSTAT( statistics ) ;
```

SORTTITLE

NM and CM callable.

Prints the version number and title of the SORTLIB segment on \$STDLIST.

```
SORTTITLE;
```

STACKDUMP

NM and CM callable.

Calls the system debugger to send a stack trace to \$STDLIST or to the file specified in the *formaldesig* parameter. Control then returns to the calling procedure.

(NM and CM)

```
          CA          I16V  I16V  I32
STACKDUMP (formaldesig,idnumber,flags,selec);
```

(CM: SPL language only)

```
          CA          I16V  I16V  I32
STACKDUMP ' (formaldesig,idnumber,flags,selec);
```

STARTSESS

NM and CM callable.

Initiates a session on the specified terminal. Programmatic sessions (PS) capability is required.

```
          I16V      CA      I16  I32  I16A
STARTSESS (ldev,logonstring,jsid,jsnum,jsstatus);
```

SUSPEND

NM and CM callable.

Suspends a process. Process handling (PH) capability is required.

```
          U16V  I16V
SUSPEND (allow, rin);
```

SWITCHDB

CM callable only.

Switches the DB register pointer. Privileged mode (PM) capability is required.

```
          U16      O-P      U16V
logindex:=SWITCHDB (index)
```

TERMINATE

NM and CM callable.

Releases all resources held by the process and its descendants are released. All remaining files, opened by the process and its descendants, are closed and assigned the same disposition they had when opened.

```
TERMINATE;
```

TIMER

NM and CM callable.

Returns system timer information.

```
I32  
count :=TIMER;
```

UNLOADPROC

NM and CM callable.

Dynamically unloads a compatibility mode (CM) segmented library (SL) procedure.

```
I16V  
UNLOADPROC(procid);
```

UNLOCKGLORIN

NM and CM callable.

Unlocks a global resource identification number (RIN) that was locked with the LOCKGLORIN intrinsic.

```
I16V  
UNLOCKGLORIN(rinum);
```

UNLOCKLOCRIN

NM and CM callable.

Unlocks a local resource identification number (RIN) that was locked by the LOCKLOCRIN intrinsic.

```
I16V  
UNLOCKLOCRIN(rinum);
```

WHO

NM and CM callable.

Returns the access mode and attributes of the user calling the intrinsic.

```
U16 I32 I32 CA CA CA CA U16  
WHO(mode,capability,localattr,username,groupname,acctname,homename,term);
```

WRITELOG

NM and CM callable.

Writes database and subsystem file records to the user logging file. User logging (LG) or system supervisor (OP) capability is required.

```
I32 U16A I16 I16 I16  
WRITELOG(index,data,length,mode,logstatus);
```

XARITRAP

NM and CM callable.

Arms or disarms the user-written arithmetic trap handling procedure.

```

      I*V  I32V  I32  I32
XARITRAP(mask,plabel,oldmask,oldplabel);

```

XCONTRAP

NM and CM callable.

Arms or disarms user-written subsystem break trap handling procedure.

```

      I*V  I*
XCONTRAP(plabel,oldplabel);

```

XLIBTRAP

NM and CM callable.

Enables or disables a user-written software library trap handling procedure.

```

      I*V  I*
XLIBTRAP(plabel,oldplabel);

```

XSYSTRAP

NM and CM callable.

Enables or disables a user-written system trap handling procedure.

```

      I*V  I*
XSYSTRAP(plabel,oldplabel);

```

ZSIZE

NM and CM callable.

Alters current DB to Z area of the compatibility mode (CM) stack.

```

      I16  I16V
newsiz:=ZSIZE(size);

```

4 FCOPY Commands

FCOPY commands

Description of all the FCOPY commands.

To Initiate FCOPY

```
RUN FCOPY.PUB.SYS

FROM[ =fromfile
      =tofile
      =*
      = ] ; TO[ = ( dfile,kfile )
              = ( tofile )
              = tofile
              =*
              = ] [ ; functionlist ]
```

Syntax of FCOPY Functions

```
[ ; NOUSERLABELS ] [ ; CCTL
                    ; NOCCTL ] [ ; NEW ]

[ ; { CLEAR
    KANA } [ ; HEX
           ; OCTAL
           ; HEXO ] [ ; NORECNUM ] [ ; TITLE=title ] ]

[ ; CHAR [ ; HEX
          ; OCTAL
          ; HEXO ] [ ; NORECNUM ] [ ; TITLE=title ] [ ; LANG= language ] ]

[ ; { HEX
    OCTAL
    HEXO } [ ; CHAR
           ; CLEAR
           ; KANA ] [ ; NORECNUM ] [ ; TITLE=title ] ]

[ ; DEBLOCK=logical-record-length ]

[ ; { EBCDICIN
    EBCDICOUT } [ = { field
                    ( field [ ; field [ ; . . . ] ] ) } [ , EXCLUDE ] [ ; LANG=language ] ] ]

[ ; { BCDICIN
    BCDICOUT
    EBCDIKIN
    EBCDIKOUT } [ = { field
                    ( field [ ; field [ ; . . . ] ] ) } [ , EXCLUDE ] ] ]

[ ; FILES = { number-of-files
             ALL } ]

[ ; IGNERR [ = number-of-errors ] ] [ ; COMPARE [ = number-of-errors ] ]

[ ; SKIPEOF = [ { +
              - } from-eofs
              from-file-number ] [ , { +
              - } to-eofs
              to-file-number ] ]

[ ; SUBSET = [ "characterstring" [ , column ] [ , EXCLUDE ]
             #patternlist# [ , column ] [ , EXCLUDE ]
             ( range [ ; range [ ; . . . ] ] ) ] ]

[ ; NOKSAM [ ; KEY [ = character-location ] ]

[ ; UPSHIFT [ ; LANG=language ] ] [ ; VERIFY [ = number-of-errors ] ]
```

FCOPY Functions

BCDICIN/BCDICOUT

BCDICIN translates from BCDIC to ASCII. BCDICOUT translates from ASCII to BCDIC.

```
; {BCDICIN
  BCDICOUT} [= {field
                (field[ ;field[ ; . . . ])]} [ , EXCLUDE]]
FCOPY FROM=FILE1 ; TO=FILE2 ; BCDICIN=(1, 5 ; 10 : 30) , EXCLUDE
```

CCTL/NOCTTL

CCTL designates the first character of each record in the *fromfile* as a carriage control character in the *tofile*; NOCTTL specifies that the first character of each record in the *fromfile* is not to be used as a carriage control character in the *tofile*.

```
; {CCTL
  NOCTTL}
FCOPY BETA ; NOCTTL
```

CHAR

Displays the contents of a file, record by record, in the form of character symbols in ASCII code.

```
; CHAR [ ; HEX
        ; HEXO
        ; OCTAL] [ ; NORECNUM] [ ; TITLE=title] [ ; LANG=language]
FCOPY FROM=DISPL ; TO= ; OCTAL ; CHAR
```

CLEAR

Displays the contents of a file, record by record, in the form of character symbols for all codes in the file.

```
; CLEAR [ ; HEX
        ; HEXO
        ; OCTAL] [ ; NORECNUM] [ ; TITLE=title]
FCOPY FROM=DISPL ; TO= ; OCTAL ; CLEAR
```

COMPARE

Compares the contents of the *fromfile* with the contents of the *tofile*, record by record, without changing either file.

```
; COMPARE [=number-of-errors]
FCOPY FROM=FILEA ; TO=DUP1 ; COMPARE
```

COPYACD

Copies the access control definition (ACD) associated with a file when the file is being copied.

```
; COPYACD
FCOPY FROM=SOURCEF ; TO=TARGETF ; COPYACD
```

COPYACD applies only to MPE V Delta 4 and subsequent releases and not to MPE/iX.

DEBLOCK

Removes a record from the blocked status.

```
;DEBLOCK=logical-record-length  
FILE TAPEBYTE;REC=-790,1,U,ASCII  
FROM=*TAPEBYTE;TO=DISC1;DEBLOCK=-79
```

EBCDICIN/EBCDICOUT

EBCDICIN translates from EBCDIC to the character code specified in the translation table of the language you select. EBCDICOUT translates from the character code specified in the translation table of the language you select to EBCDIC. When you do not specify a language, EBCDICIN translates from EBCDIC to ASCII, and EBCDICOUT translates from ASCII to EBCDIC.

```
{ EBCDICIN  
  EBCDICOUT }  
[={field  
  (field [ ;field [ ; . . . ] ] ) } [ , EXCLUDE ] [ ; LANG=language ] ]  
FROM=*TAPE;TO=DISC1;EBCDICIN=3:7,14:27
```

EBCDIKIN/EBCDIKOUT

EBCDIKIN translates from EBCDIK (IBM Standard) to JIS (Japanese Industrial Standard). EBCDIKOUT translates from JIS to EBCDIK.

```
{ EBCDIKIN  
  EBCDIKOUT } [={field  
  (field [ ;field [ ; . . . ] ] ) } [ , EXCLUDE ] ]  
FROM=FILE1;TO=FILE2;EBCDIKIN=3:6,EXCLUDE
```

FILES

Copies multiple files from unlabeled magnetic tapes, serial disks, and cartridge tapes. FCOPY copies only one file if you do not use the FILES function.

```
;FILES={number-of-files  
  ALL }  
FROM=*TAPEA;TO=*TAPEB;FILES=3;SUBSET=11:25
```

HEX

Displays the contents of a file, record by record, in the form of character code numbers in hexadecimal form.

```
;HEX [ ; CHAR  
  ; CLEAR  
  ; KANA ] [ ; NORECNUM ] [ ; TITLE=title ]  
FROM=TEXT3;TO=*LP;HEX;CHAR;  
TITLE="TITLE LINE FOR CHAR/HEX DISPLAY EXAMPLE"
```

HEXO

Displays the contents of a file, record by record, in the form of character code numbers, the data in hexadecimal form, and the record number in octal form.

```
;HEXO[ ;CHAR
;CLEAR
;KANA][ ;NORECNUM][ ;TITLE=title ]
FROM=TEXT3;TO=*LP;HEXO;CHAR;
TITLE="TITLE LINE FOR CHAR/HEX DISPLAY EXAMPLE"
```

IGNERR

Bypasses errors in a magnetic tape *fromfile* and reports each ignored error.

```
;IGNERR[=number-of-errors ]
FROM=*TAPE;TP=FILE3;SUBSET;IGNERR=5
```

KANA

Displays the contents of a file, record by record, in the form of JIS character symbols. KANA displays symbols not represented by characters in JIS code as decimal points.

```
;KANA[ ;HEX
;HEXO
;OCTAL][ ;NORECNUM][ ;TITLE=title ]
; KANA;OCTAL;TITLE="KANA symbols in OCTAL"
```

KEY

Chooses a key sequence in which to copy KSAM files. The KEY function works only with KSAM *fromfiles*.

```
;KEY [=character-location ]
FROM=KSAM;TO=ALPHA;KEY=21
```

NEW

Creates a new permanent disk file as the *tofile*.

```
;NEW
FROM=OLDSTUFF;TO=NEWFILE;NEW
```

NOKSAM

Copies the data file of a KSAM file into another, non-KSAM file.

```
;NOKSAM
FROM=KSAMFILE;TO=FILEX;NOKSAM;NOUSERLABELS
```

NOUSERLABELS

NOUSERLABELS lets you omit user labels when copying from a tape or disk file to another file.

```
;NOUSERLABELS
FROM=*TAPEA;TO=DISC;NOUSERLABELS
```

OCTAL

Lets you display the contents of a file, record by record, in the form of character code numbers in octal form.

FCOPY Commands

FCOPY commands

```
;OCTAL[ ;CHAR  
;CLEAR  
;KANA ][ ;NORECNUM][ ;TITLE=title]  
FROM=TEXT3;TO=*LP;OCTAL
```

SKIPEOF

SKIPEOF instructs FCOPY to skip end-of-file markers on a serial storage device, in order to position the device at the desired file before copying. SKIPEOF is not applicable to labeled tapes.

```
;SKIPEOF=[ {+  
-}from-eofs  
from-file-number][ , {+  
-}to-eofs  
to-file-number]  
FROM=*THISTAPE;TO=*THATTAPE;SKIPEOF=4,5
```

SUBSET

SUBSET lets you copy only a specific portion (subset) of a file. You can define the subset in one of two ways, either as all records with a certain character string or numeric pattern beginning in a specific column, or as a set of continuous records.

```
;SUBSET[="characterstring" [ , column ] [ , EXCLUDE ]  
=#patternlist# [ , column ] [ , EXCLUDE ]  
=(range[ ; range ] [ ; . . . ] )  
FROM=MASTER;TO=MEN;SUBSET="MALE" , 17
```

UPSHIFT

UPSHIFT converts lowercase Roman alphabetic characters to uppercase as part of the copying operation.

```
;UPSHIFT[ ;LANG=language ]  
FROM=LOWER;TO=UPPER;UPSHIFT
```

VERIFY

VERIFY compares the contents of the *tofile* with the contents of the *fromfile*, record by record, immediately after a copy operation.

```
;VERIFY[=number-of-errors ]  
FROM=OLDDISC;TO=COPY;VERIFY
```

5 SORT-MERGE/XL Commands

Description of SORT-MERGE/XL Commands

To Initiate SORT

```
RUN SORT.PUB.SYS
```

ALTSEQ

The ALTSEQ command defines a collating sequence other than the standard ASCII or EBCDIC format. The ALTSEQ command must be preceded by a DATA command. It is effective only if the keys are of *type* BYTE and if the input data is ASCII.

```
A[LTSEQ]modspec1[ ,modspec2]...[ , modspecN]
```

```
[EACH]leftspec {=  
                <blank>  
                WITH} rightspec
```

or

```
MERGE leftspec {WITH  
                <blank>  
                = } rightspec
```

To specify *leftspec* and *rightspec* use the following form:

```
{string  
 num byte  
 range string }
```

DATA

Specifies the type of the input data (either ASCII or EBCDIC) and the basic collating sequence to be used in the particular SORT/XL (or MERGE/XL) operation. The collating sequence may be altered, if desired, by using the ALTSEQ command.

```
DATA [IS] {A[SCII]  
          E[BCDIC]} [ , ] SEQ[UENCE] [IS]{ A[SCII]  
                                           E[BCDIC]}
```

END

Specifies the conclusion of SORT-MERGE/XL parameters. It also starts the sort or merge operation specified.

```
E[ND]
```

EXIT

Terminates the operation of SORT/XL or MERGE/XL and exits the subsystem.

```
EX[IT]
```

INPUT (SORT/XL)

Within the SORT/XL subsystem, the INPUT command specifies the input file(s) to be sorted. Refer to the MERGE/XL INPUT command for information on how to use the command within that subsystem.

```
I[INPUT]  { $STDIN [ X ]
           *
           fname
           (filename1,filename2,...filenameN) } [ , #records ] [ , rec size ]
```

KEY

Specifies the location of the key data items in a file's records which are to be sorted or merged.

```
K[KEY]  keyspec1 [ ; keyspec2 ] . . . [ ; keyspecN ]
```

keyspec A group of parameters used to specify a key data item to be sorted or merged. The syntax of the *keyspec* parameters follows:

```
position, length [ , type ] [ , DESC ]
```

LANGUAGE

Defines the native language whose collating sequence is to be used to sort keys of type CHARACTER.

```
L[LANGUAGE] [ IS ]    { langnum
                       <blank>
                       langname }
```

OUTPUT (SORT/XL)

Designates and creates the output file which is to receive the sorted records. Refer to the MERGE/XL OUTPUT command for information on how to use the command within that subsystem.

```
O[OUTPUT]  { *
           $STDLIST
           filename } [ , NUM ] [ , KEY ]
```

RESET

The RESET command is used to correct errors made in the specification of keys. When entered, it nullifies all existing KEY commands.

```
RESET
```

SHOW

Displays the collating sequence or the translation table.

Description of SORT-MERGE/XL Commands

```
SH[OW] {S[EQUENCE][,O[FFLINE
        T[ABLE][,O[FFLINE
        <blank>
        NOS[EQUENCE]
        NOT[ABLE]          }
```

VERIFY

Displays information on the input and output files, key descriptions, and the various options in effect during a SORT/XL or MERGE/XL operation to the file LIST.

```
V[ERIFY]
```

:(MPE Command)

The **:** is entered preceding MPE commands within SORT/XL or MERGE/XL, for example, for entering file equations.

```
: [MPE command]
```

:EOD

The **:EOD** command is not truly a command. It terminates the list of input records to MERGE/XL when * (for \$STDIN) is the input file.

```
:EOD
```

To Initiate MERGE

```
RUN MERGE.PUB.SYS
```

ALTSEQ

The ALTSEQ command defines a collating sequence other than the standard ASCII or EBCDIC format. The ALTSEQ command must be preceded by a DATA command. It is effective only if the keys are of *type* BYTE and if the input data is ASCII. (Refer to Appendix B of the *Sort-Merge/XL General User's Guide* for information on ASCII and EBCDIC character set values.)

```
A[LTSEQ] modspec1[, modspec2]..[, modspecN]
```

```
[EACH]leftspec { =
                  <blank>
                  WITH} rightspec
```

```
or
MERGE leftspec {WITH
                 <blank>
                 = } rightspec
```

To specify *leftspec* and *rightspec* use the following form:

```
{string
 num byte
 range string }
```

DATA

Specifies the type of the input data (either ASCII or EBCDIC) and the basic collating sequence to be used in the particular SORT/XL (or MERGE/XL) operation. The collating sequence may be altered, if desired, by using the ALTSEQ command.

```
DATA [IS] {A[SCII]
           E[EBCDIC]} [ , ] SEQ[UENCE] [IS] {A[SCII]
                                           E[EBCDIC]}
```

END

Specifies the conclusion of SORT-MERGE/XL parameters. It also starts the sort or merge operation specified.

```
E[ND]
```

EXIT

Terminates the operation of SORT/XL or MERGE/XL and exits the subsystem.

```
EX[IT]
```

INPUT (MERGE/XL)

Within the MERGE/XL subsystem, the INPUT command specifies the sorted files to be merged. Refer to the SORT/XL INPUT command for information on how to use the command within that subsystem.

```
I[INPUT] {filename1,filename2}[ ,filename3]...[ ,filenameN]
```

KEY

Specifies the location of the key data items in a file's records which are to be sorted or merged.

```
K[EY] keyspec1 [; keyspec2]...[; keyspecN]
```

keyspec

A group of parameters used to specify a key data item to be sorted or merged. The syntax of the *keyspec* parameters follows:

```
position, length [ , type ] [ , DESC]
```

LANGUAGE

Defines the native language whose collating sequence is to be used to sort keys of type CHARACTER.

```
L[ANGUAGE][IS] {langnum
                 <blank>
                 langname}
```

OUTPUT (MERGE/XL)

The OUTPUT command is used to designate and create the output file, which is to receive the merged records. Refer to the SORT/XL OUTPUT command for information on how to use the command within that subsystem.

```
O[UTPUT] {filename  
<blank>  
$STDLIST}[ , num records][ , KEY]
```

RESET

The RESET command is used to correct errors made in the specification of keys. When entered, it nullifies all existing KEY commands.

```
RESET
```

SHOW

Displays the collating sequence or the translation table.

```
SH[OW] {S[EQUENCE][ ,O[FFLINE  
T[ABLE][ ,O[FFLINE  
<blank>  
NOS[EQUENCE]  
NOT[ABLE] }
```

VERIFY

Displays information on the input and output files, key descriptions, and the various options in effect during a SORT/XL or MERGE/XL operation to the file LIST.

```
V[ERIFY]
```

:(MPE Command)

The : is entered preceding MPE commands within SORT/XL or MERGE/XL.

```
: [MPE command]
```

:EOD

The :EOD command is not truly a command. It terminates the list of input records to SORT/XL when * (for \$STDIN) is the input file.

```
:EOD
```

6 System Debug

System Debug provides a family of low-level assembly language debuggers for MPE/iX:

Debugging your system

- Debug
- Dump Analysis Tool (DAT)
- Standalone Analysis Tool (SAT)

This chapter presents short descriptions of System Debug commands, window commands, standard functions, and environment variables. Refer to the *System Debug Reference Manual* for additional details on System Debug commands and functions described in this chapter.

System Debug Command Descriptions

This section presents short descriptions of System Debug commands. Commands that are inappropriate in either DAT or Debug are identified as "DAT only" or "Debug only". In addition, commands that require privileged mode (PM) capability are identified.

:

The CI command - Access to the MPE/iX command interpreter (CI).

: [*command*]

=

The calculator command. Calculates the value of an expression and displays the result in the specified base.

= *expression* [*base*]

ABORT

Aborts/terminates the current System Debug process.

ABORT

ALIAS

Defines an alias (alternative) name for a command or macro.

ALIAS *name command*

ALIASD[EL]

Deletes the specified alias(es).

ALIASD[EL] *pattern* [*group*]

ALIASINIT

Restores the predefined aliases, in case they have been deleted.

ALIASINIT

ALIASL[IST]

Lists the currently defined aliases.

ALIAS[LIST] [*pattern*] [*group*]

B (break)

Debug only. Privileged Mode: BA, BAX, BS.

Break. Sets a breakpoint.

B	<i>logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Program
BG	<i>logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Group library
BP	<i>logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Account library
BLG	<i>logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Logon group lib
BLP	<i>logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Logon account lib
BS	<i>logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	System library
BU	<i>fname logaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	User library
EV	<i>virtaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Virtual address
BA	<i>cmabsaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Absolute CST
BAX	<i>cmabsaddr</i>	[<i>:pin</i> @]	[<i>count</i>]	[<i>loud</i>]	[<i>cmdlist</i>]	Absolute CSTX

BD

Debug only.

Breakpoint delete. Deletes a breakpoint entry specified by index number.

BD [*number* | @ [*: pin* | @]]

BL

Debug only.

Breakpoint list. Lists breakpoint entries, specified by index number.

BL [*number* | @ [*: pin* | @]]

CLOSEDUMP

DAT only.

Closes a dump file.

CLOSEDUMP

CM

Enters compatibility mode (cmdat/cmdebug). See the NM command.

CM

CMDL[IST]

Command list. Displays a list of the valid commands for System Debug.

```
CMDL[IST] [pattern] [group] [options]
```

CMG

Privileged Mode

Displays values in the CMGGLOBALS record for a process.

```
CMG [pin]
```

C[ONTINUE]

Continues/resumes execution of user program.

```
C[ONTINUE]  
C[ONTINUE] [IGNORE]  
C[ONTINUE] [NOIGNORE]
```

D (display)

Privileged Mode: DA, DCS, DCA, DZ, DSEC.

Displays the contents of the specified address.

DA	<i>offset</i>	[count]	[base]	[recw]	[bytew]	ABS relative
DD	<i>dst.off</i>	[count]	[base]	[recw]	[bytew]	CM data segment
DDB	<i>offset</i>	[count]	[base]	[recw]	[bytew]	DB relative
DS	<i>offset</i>	[count]	[base]	[recw]	[bytew]	S relative
DQ	<i>offset</i>	[count]	[base]	[recw]	[bytew]	Q relative
DC	<i>logaddr</i>	[count]	[base]	[recw]	[bytew]	Program file
DCG	<i>logaddr</i>	[count]	[base]	[recw]	[bytew]	Group library
DCP	<i>logaddr</i>	[count]	[base]	[recw]	[bytew]	Account library
DCLG	<i>logaddr</i>	[count]	[base]	[recw]	[bytew]	Logon group lib
DCLP	<i>logaddr</i>	[count]	[base]	[recw]	[bytew]	Logon account lib
DCS	<i>logaddr</i>	[count]	[base]	[recw]	[bytew]	System library
DCU	<i>fname logaddr</i>	[count]	[base]	[recw]	[bytew]	User library
DCA	<i>cmabsaddr</i>	[count]	[base]	[recw]	[bytew]	Absolute CST
DCAX	<i>cmabsaddr</i>	[count]	[base]	[recw]	[bytew]	Absolute CSTX
DV	<i>virtaddr</i>	[count]	[base]	[recw]	[bytew]	Virtual
DZ	<i>realaddr</i>	[count]	[base]	[recw]	[bytew]	Real memory
DSEC	<i>ldev.off</i>	[count]	[base]	[recw]	[bytew]	Secondary store

DATAB

Debug only. Privileged Mode.

Sets a data breakpoint.

```
DATAB virtaddr [:pin|@] [byte_count] [count] [loudness] [cmdlist]
```

DATABD

Debug only. Privileged Mode.

Deletes a data breakpoint entry specified by index number.

```
DATABD [number | @ [: pin | @ ] ]
```

DATABL

Debug only. Privileged Mode.

Lists data breakpoint entries, specified by index number.

```
DATABL [number | @ [: pin | @] ]
```

DEBUG

Debug only. Privileged Mode.

DEBUG command access to DEBUG XL.

```
DEBUG
```

DELETE_{xxx}

Delete various items. These are predefined aliases for other commands.

```
DELETEDB      alias for BD
DELETEALIAS   alias for ALIASD
DELETEERR     alias for ERRD
DELETEMAC     alias for MACD
DELETEVAR     alias for VARD
```

DEMO

Privileged Mode.

Adds/deletes/lists terminals used for demonstrating System Debug.

```
DEMO
DEMO LIST
DEMO ADD      ldevs
DEMO DELETE  ldevs
```

DIS

Disassembles a single NM or CM assembly instruction, based on the current mode.

```
DIS nmword [virtaddr]
DIS cmword1 [cmword2] [cmlogaddr]
```

DO

Reexecutes a command from the command stack.

```
DO [cmd_string ]
DO [history_index]
```

DPIB

DAT Privileged Mode.

Display data from the process identification block (PIB) for a process.

```
DPIB [pin]
```

DPTREE

DAT Privileged Mode.

Prints out the process tree starting at the given PIN.

```
DPTREE [pin]
```

DR

Displays contents of the CM or NM registers.

```
DR [cm_register] [base]  
DR [nm_register] [base]
```

DUMPINFO

DAT Privileged Mode.

Displays dump file information.

```
DUMPINFO [options]
```

ENV

Assigns a new value to one of the predefined environment variables.

```
ENV var_name [=] var_value
```

ENVL[IST]

Displays the current values for environmental variables.

```
ENVL[IST] [pattern] [group] [options]
```

ERR

Pushes a user error message onto the error command stack.

```
ERR errmsg
```

ERRD[EL]

Deletes all errors on the error stack (reset the stack).

```
ERRD[EL]
```

ERRL[IST]

Error list. Lists the most recent error(s) on the error stack.

```
ERRL[IST] [ALL]
```

E[XIT]

Exits/resumes execution of user program.

```
E[XIT]          Same as CONTINUE (in Debug)  
E[XIT]          Exit program      (in DAT)
```

F (format)

Formats a specified data structure.

```
FT                path ft_options
FV  virtaddr path fv_options
```

F (freeze)

Debug only. Privileged Mode.

Freezes a code segment, data segment, or virtual address (range) in memory.

FC	<i>logaddr</i>	[<i>bytelength</i>]	Program file
FCG	<i>logaddr</i>	[<i>bytelength</i>]	Group library
FPCP	<i>logaddr</i>	[<i>bytelength</i>]	Account library
FCLG	<i>logaddr</i>	[<i>bytelength</i>]	Logon group library
FCLP	<i>logaddr</i>	[<i>bytelength</i>]	Logon account library
FCS	<i>logaddr</i>	[<i>bytelength</i>]	System library
FCU	<i>fname logaddr</i>	[<i>bytelength</i>]	User library
FCA	<i>cmabsaddr</i>		CM absolute CST
FCAX	<i>cmabsaddr</i>		CM absolute CST
FDA	<i>dstoff</i>		CM data segment
FVA	<i>virtaddr</i>	[<i>bytelength</i>]	Virtual address

FINDPROC

Debug Privileged Mode.

Dynamically loads a specified NM procedure from any NM library.

```
FINDPROC procedurename library_file [ [NO]IGNORECASE]
```

FOREACH

Each time a FOREACH command is executed, *name* is set to the next expression value in *value_list* prior to the execution of *cmdlist*. Execution ends when there are no more expression values in the *value_list*.

```
FOREACH name value_list command
FOREACH name value_list { cmdlist }
```

FPMAP

Reinitializes CM FPMAP symbolic procedure name access.

```
FPMAP
```

FUNCL[IST]

Function list. Displays information about the predefined functions.

```
FUNCL[IST] [pattern] [group] [options]
```

GETDUMP

DAT Privileged Mode.

Reads in a dump tape and creates a dump file.

```
GETDUMP file [ ldevlist ]  
GETDUMP file [ DIR ]
```

H[ELP]

Displays online help messages for System Debug.

```
H[ELP] [topic] [options]
```

HIST[ORY]

Displays the history command stack.

```
HIST[ORY] option
```

IF

If *condition* evaluates to TRUE, then execute all commands in *cmdlist*, else execute all commands in *cmdlist2*.

```
IF condition THEN command  
IF condition THEN { cmdlist }  
IF condition THEN command1 ELSE command2  
IF condition THEN { cmdlist } ELSE command2  
IF condition THEN command1 ELSE { cmdlist2 }  
IF condition THEN { cmdlist } ELSE { cmdlist2 }
```

IGNORE

Protects the next command (list) from error bailout.

```
IGNORE option
```

INITxx

Privileged Mode.

Initialize registers from a specified location.

```
INITNM virtaddr [ISM | PIMREAL | PIMVIRTUAL]  
INITCM virtaddr [ISM | PIMREAL | PIMVIRTUAL]  
  
INITNM TCB  
INITCM TCB | CMG | REGS
```

KILL

Debug only

Privileged Mode

Issues a request to process management to kill the specified process.

```
KILL pin
```

LEV

Sets the current environment to the specified stack level in the stack markers.

```
LEV [number]  
LEV [number] [interrupt_level]
```

LIST

Controls the recording of input and output to a list file.

```
LIST  
LIST [filename]  
LIST [ON ]  
LIST [OFF ]  
LIST [CLOSE]
```

LISTREDO

Displays the history command stack.

```
LISTREDO          alias for HIST[ORY]
```

LOADINFO

Debug only

Lists information about the currently loaded program and libraries.

```
LOADINFO
```

LOADPROC

Debug only.

Dynamically loads a specified CM procedure from a logically specified CM library selector.

```
LOADPROC procedurename libselect
```

LOC

Defines a local variable within a macro body.

```
LOC var_name [:var_type] [=] var_value
```

LOCL[IST]

Lists the local variables that are defined with a macro.

```
LOCL[IST] [pattern]
```

LOG

Controls the recording of user input to the logfile.

```
LOG
LOG [filename]
LOG [ON ]
LOG [OFF ]
LOG [CLOSE]
```

M (modify)

Debug only. Privileged Mode: MA, MD, MCS, MZ, MSEC.

Modifies the contents of the specified number of words at the specified address.

MA	<i>offset</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	ABS relative
MD	<i>dst.off</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Data segment
MDB	<i>offset</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	DB relative
MS	<i>offset</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	S relative
MQ	<i>offset</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Q relative
MC	<i>logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Program file
MCG	<i>logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Group library
MCP	<i>logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Account library
MCLG	<i>logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Logon group
MCLP	<i>logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Logon account
MCS	<i>logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	System library
MCU	<i>fname logaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	User library
MCA	<i>cmabsaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Absolute CST
MCAX	<i>cmabsaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Absolute CSTX
MV	<i>virtaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Virtual
MZ	<i>realaddr</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Real memory
MSEC	<i>ldev.off</i>	[<i>count</i>]	[<i>base</i>]	[<i>newvalue(s)</i>]	Secondary storem

MAC[RO]

Defines a macro.

```
MAC[RO] name {body}
MAC[RO] name [ (parameters) ] {body}
MAC[RO] name [ (parameters) ] [options] {body}
```

MACD[EL]

Macro delete. Deletes the specified macro definition(s).

```
MACD[EL] pattern
```

MACECHO

Controls the "echoing" of each macro command line prior to its execution.

```
MACECHO pattern [level]
```

MACL[IST]

Macro list. Lists the specified macro definition(s).

```
MACL[IST] [pattern] [options]
```

MACREF

Resets the reference count to zero for the specified macro(s).

`MACREF pattern`

MACTRACE

Controls the "tracing" of macro execution.

`MACTRACE pattern [level]`

MAP

Opens a file and maps it into a usable virtual address space.

`MAP filename [option]`

MAPL[IST]

Lists the specified file(s) that have been opened with the MAP command.

`MAPL[IST] [pattern]`

MODD

DAT Privileged Mode.

Modification delete. Deletes a modification entry specified by index number.

`MODD [index
@]`

MODL

DAT only.

Modification list. Lists current dump modifications.

`MODL [index
@]`

MPEXL

Privileged Mode.

Displays information about the files which were used to build the operating system SOM portion of the NL.Pub.SYS for MPE/iX.

`MPEXL [fileset] [optionstring] [outputfile]`

MPSW

Privileged Mode.

Modifies the NM processor status word (PSW). Exercise a bit of care with this command.

`MPSW bit_string`

MR

Modifies the contents of the specified CM or NM register.

```
MR cm_register [newvalue]  
MR nm_register [newvalue]
```

NM

Enters native mode (nm-dat / nm-debug). See the CM command.

```
NM
```

OPENDUMP

DAT Privileged Mode.

Opens a dump file.

```
OPENDUMP file
```

PAUSE

Pauses (puts to sleep) a process for the specified number of seconds.

```
PAUSE n
```

PIN

Privileged Mode.

Switches the process-specific pointers and registers to allow the examination of process related information.

```
PIN [pin] [ANYSSTATE]
```

PROCLIST

Lists the specified NM symbols in the specified NM executable library.

```
PROCLIST [pattern] [lstfile] [lookup_id] [detail] [outputfile]
```

PURGEDUMP

DAT Privileged Mode.

Purges a dump file.

```
PURGEDUMP file
```

REDO

Reexecutes a command from the history command stack after optionally editing the command.

```
REDO [cmd_string ]  
REDO [history_index]
```

REGLIST

Lists the registers into a file in USE file format.

```
REGLIST [filename]
```

RESTORE

Restores macros or variables from a file that was previously created by the STORE command.

```
RESTORE MACROS filename
RESTORE VARIABLES filename
```

RET[URN]

Exits from a macro, optionally returning a specified value.

```
RET[URN] [value]
```

SET

Set new values for a select subset of all user configurable options.

```
SET
SET [ O[CT] | %
      D[EC] | #
      H[EX] | $ ] [ IN
                  OUT ]
SET [ CRON
      CROFF ]
SET [ MOREON
      MOREOFF ]
SET [ DEF[AULT] ]
```

SETxxx

The SETxxx commands are predefined aliases for other commands.

```
SETALIAS alias for ALIAS
SETENV alias for ENV
SETERR alias for ERR
SETLOC alias for LOC
SETMAC alias for MAC
SETVAR alias for VAR
```

SHOWxxx

The SHOWxxx commands are predefined aliases for other commands.

```
SHOWALIAS alias for ALIASL
SHOWB alias for BL
SHOWCMD alias for CMDL
SHOWDATAB alias for DATABL
SHOWENV alias for ENVL
SHOWERR alias for ERRL
SHOWFUNC alias for FUNCL
SHOWLOC alias for LOCL
SHOWMAC alias for MACL
SHOWMAP alias for MAPL
```

```
SHOWSET      alias for SET
SHOWSYM      alias for SYML
SHOWVAR      alias for VARL
```

S, SS

Single steps.

```
S[S] [num_instrs] [ L[OUD] | Q[UIET] ]
```

STORE

Stores the currently defined macros or variables to a file.

```
STORE MACROS   filename
STORE VARIABLES filename
```

SYMCLOSE

Closes a symbolic data type file that was opened with the SYMOPEN command.

```
SYMCLOSE symname
```

SYMF[ILES]

Lists all open symbolic data type files and their symbolic names.

```
SYMF[ILES]
```

SYMINFO

Lists information/dump data for an opened symbolic data type file.

```
SYMINFO [symname] [option] [offset] [length]
```

SYML[IST]

Lists information for the specified symbol name in an opened symbolic data type file.

```
SYML[IST] [pattern] [symname] [option]
```

SYMOPEN

Opens a symbolic data type file and sets up pointers to the symbolic debug records.

```
SYMOPEN filename [symname]
```

SYMPREP

Prepares a program file containing symbolic debug information to be used by the symbolic formatter/symbolic access facility. Files modified through the use of this command are referred to as symbolic data type files.

```
SYMPREP filename
```

T (translate)

Privileged Mode: TCA, TCS.

Translates the specified CM address to a virtual address.

TA	<i>offset</i>	ABS - Bank0
TD	<i>dst.off</i>	Data segment
TDB	<i>offset</i>	DB relative
TS	<i>offset</i>	S relative
TQ	<i>offset</i>	Q relative
TC	<i>cmlogaddr</i>	Program file
TCG	<i>cmlogaddr</i>	Group library
TCP	<i>cmlogaddr</i>	Account library
TCLG	<i>cmlogaddr</i>	Logon group library
TCLP	<i>cmlogaddr</i>	Logon account library
TCS	<i>cmlogaddr</i>	System library
TCA	<i>cmabsaddr</i>	Absolute CST
TCAX	<i>cmabsaddr</i>	Absolute CSTX

TERM

Debug only.

Controls the synchronization of several debug processes on a single terminal.

```
TERM
TERM LIST
TERM NEXT
```

TR[ACE]

Displays a stack trace.

```
TR[ACE] [level] [options]
```

TRAP

Debug only.

Arms/disarms/lists various traps that are monitored by Debug.

```
TRAP [LIST]
TRAP [trap-name] [option]
```

UF

Debug Privileged Mode.

Unfreezes a code segment, data segment, or virtual address (range) in memory.

UFC	<i>logaddr</i>	[<i>bytlength</i>]	Program file
UFCG	<i>logaddr</i>	[<i>bytlength</i>]	Group library
UFCE	<i>logaddr</i>	[<i>bytlength</i>]	Account library
UFCLG	<i>logaddr</i>		Logon group library
UFCLP	<i>logaddr</i>		Logon account library
UFCS	<i>logaddr</i>	[<i>bytlength</i>]	System library
UFCE	<i>fname</i>	<i>logaddr</i> [<i>bytlength</i>]	User library
UFCA	<i>cmabsaddr</i>		Absolute CST
UFCE	<i>cmabsaddr</i>		Absolute CSTX

System Debug

Debugging your system

```
UFDA dst.off                                CM data segment
UFVA virtaddr [bytelength]                 Virtual address
```

UNMAP

Closes (unmaps) a file that was opened by the MAP command.

```
UNMAP index
```

UPD

Update the windows.

```
UPD
```

USE

System Debug commands can be executed from a file with the USE command.

```
USE
USE [filename] [count]
USENEXT count
USE [CLOSE][ALL | @]
```

VAR

Defines a user-defined variable.

```
VAR var_name [:var_type] [=] var_value
```

VARD[EL]

Variable delete. Deletes the specified user-defined variable(s).

```
VARD[EL] pattern
```

VARL[IST]

Variable list. Lists the value(s) for the specified user-defined variable(s).

```
VARL[IST] [pattern]
```

W (write)

Writes a list of values, with optional formatting, to output.

```
W valuelist
WL valuelist
WP valuelist
```

```
WCOL column
WPAGE
```

WHELP

Displays online help messages for the window commands.

```
WHELP
```

WHILE

While *condition* evaluates to TRUE, executes all commands in *cmdlist*.

```
WHILE condition DO cmdlist
```

XL

Utilizes symbol information in a local library/program file.

```
XL localfile space_id [loaded-fname]
```

XLD

Closes files opened with the XL command.

```
XLD localfile
```

XLL

Lists all of the files that have been opened with the XL command.

```
XLL
```

Window Commands

This section presents short descriptions of System Debug window commands.

RED

Redraws the entire screen display of windows.

```
RED
```

UWm

Allocates a named user window at the specified address. The command name specifies which type of window to define. User windows are displayed within the group window.

UWA	<i>offset</i>	[<i>name</i>]	Absolute memory relative (ABS)
UWDB	<i>offset</i>	[<i>name</i>]	DB relative
UWS	<i>offset</i>	[<i>name</i>]	S relative
UWQ	<i>offset</i>	[<i>name</i>]	Q relative
UWD	<i>dst.off</i>	[<i>name</i>]	Data segment and offset
UWCA	<i>cmabsaddr</i>	[<i>name</i>]	Code (CST) segment and offset
UWCAX	<i>cmabsaddr</i>	[<i>name</i>]	Code (CSTX) segment and offset
UWV	<i>virtaddr</i>	[<i>name</i>]	Virtual address
UWZ	<i>realaddr</i>	[<i>name</i>]	Real address

WDEF

Window defaults. Resets the default window sizes.

```
WDEF
```

WGRP

Changes to the specified group of user-defined windows.

WGRP [*group_number*]

WOFF

Windows OFF. Turns off the windows.

WOFF

WON

Windows ON. Turns on the windows. If windows are already on, redraws them.

WON

wB

Window back. Scrolls the specified window backwards.

PB	[<i>amount</i>]	Program, current mode
CMPB	[<i>amount</i>]	CM program
NMPB	[<i>amount</i>]	NM program
QB	[<i>amount</i>]	CM frame, Q relative
SB	[<i>amount</i>]	CM stack, S relative
GB	[<i>amount</i>]	Group window
UB	[<i>amount</i>] [<i>win_number</i>]	User window
VB	[<i>amount</i>] [<i>win_number</i>]	Virtual window
ZB	[<i>amount</i>]	Real memory window
LB	[<i>amount</i>]	LDEV window
TXB	[<i>amount</i>] [<i>win_number</i>]	Text window

wC

Window current. Marks the specified window as the current window. Many user window (U), text window (TX), and virtual window (V) commands operate on the current window.

UC [*win_number*]
VC [*win_number*]
TXC [*win_number*]

wD

Window disable.

RD	CM registers
GRD	NM general registers
SRD	NM special registers
PD	Program, current mode
CMPD	CM program
NMPD	NM program
QD	CM frame, Q relative
SD	CM stack, S relative
GD	Group window
UD	[<i>win_number</i>] User window

VD	[win_number]	Virtual window
ZD		Real memory window
LD		LDEV window
TXD	[win_number]	Text window

wE

Window enable.

RE		CM registers
GRE		NM general registers
SRE		NM special registers
PE		Program, current mode
CMPE		CM program
NMPE		NM program
QE		CM Frame, Q relative
SE		CM Stack, S relative
GE		Group window
UE	[win_number]	User window
VE	[win_number]	Virtual window
ZE		Real memory window
LE		LDEV window
TXE	[win_number]	Text window

wF

Window forward. Scrolls the specified window forward.

PF	[amount]	Program current mode
CMPF	[amount]	CM program
NMPF	[amount]	NM program
QF	[amount]	CM frame, Q relative
SF	[amount]	CM stack, S relative
GF	[amount]	Group window
UF	[amount] [win_number]	User window
VF	[amount] [win_number]	Virtual window
ZF	[amount]	Real memory window
LF	[amount]	LDEV window
TXF	[amount] [win_number]	Text window

wH

Window home. Returns a window to its original location.

RH		CM registers window
GRH		NM general registers window
SRH		NM special registers window
PH		Program window, current mode
CMPH		CM program window
NMPH		NM program window
QH		CM frame window - Q relative
SH		CM stack window - S relative
GH		Group window
UH	[win_number]	User window
VH	[virtaddr] [win_number]	Virtual window
ZH	[realaddr]	Real memory window
LH	[ldev.off]	LDEV window
TXH	[win_number]	Text window

wI

Window information. Prints information about the indicated windows. This command is defined for the virtual (V) and text (TX) windows.

```
VI [win_number]
TXI [win_number]
```

wJ

Window jump. Jumps window to the specified address.

```
PJ [logaddr] Program file
PJG [logaddr] Group library
PJP [logaddr] Account library
PJLG [logaddr] Logon group library
PJLP [logaddr] Logon account library
PJS [logaddr] System library
PJU [fname logaddr] User library
PJV [virtaddr] Any virtual address
PJA [absaddr] Absolute CST
PJAX [absaddr] Absolute CSTX

CMPJ [logaddr] Program file
CMPJG [logaddr] Group library
CMPJP [logaddr] Account library
CMPJLG [logaddr] Logon group library
CMPJLP [logaddr] Logon account library
CMPJS [logaddr] System library
CMPJA [absaddr] Absolute CST
CMPJAX [absaddr] Absolute CSTX

NMPJ [logaddr] Program file
NMPJG [logaddr] Group library
NMPJP [logaddr] Account library
NMPJLG [logaddr] Logon group library
NMPJLP [logaddr] Logon account library
NMPJS [logaddr] System library
NMPJU [fname logaddr] User library

QJ [dst.off] CM Frame, Q relative
SJ [dst.off] CM Stack, S relative

VJ [virtaddr] [win_number] Virtual window
ZJ [realaddr] Real memory window
LJ [Ldev.off] LDEV window
TXJ [record_number] Text window
```

wK

Window kill.

```
RK CM registers
GRK NM general registers
SRK NM special registers

PK Program, current mode
CMPK CM program
NMPK NM program
QK CM frame, Q relative
SK CM stack, S relative

GK Group window
UK [win_number] User window

VK [win_number] Virtual window
ZK Real memory window
LK LDEV window
TXK [win_number] Text window
```

wL

Window lines. Sets the number of lines in a window.

RL	[<i>numlines</i>]	CM registers
GRL	[<i>numlines</i>]	NM general registers
SRL	[<i>numlines</i>]	NM special registers
PL	[<i>numlines</i>]	Program, current mode
CMPL	[<i>numlines</i>]	CM program
NMPL	[<i>numlines</i>]	NM program
QL	[<i>numlines</i>]	CM frame, Q relative
SL	[<i>numlines</i>]	CM stack, S relative
GL	[<i>numlines</i>]	Group window
UL	[<i>numlines</i>] [<i>win_number</i>]	User window
VL	[<i>numlines</i>] [<i>win_number</i>]	Virtual window
ZL	[<i>numlines</i>]	Real memory window
LL	[<i>numlines</i>]	LDEV window
TXL	[<i>numlines</i>] [<i>win_number</i>]	Text window

wM

Window mode. Changes the mode for the Q or S window.

QM	[<i>addressmode</i>] [<i>signed</i>]
SM	[<i>addressmode</i>] [<i>signed</i>]

wN

Renames a virtual window or a user-defined window.

UN	[<i>name</i>] [<i>win_number</i>]	User window
VN	[<i>name</i>] [<i>win_number</i>]	Virtual window

wR

Sets the radix (output base) for the specified window.

RR	<i>base</i>	CM registers
PR	<i>base</i>	Program, current mode
CMPR	<i>base</i>	CM program
NMPR	<i>base</i>	NM program
QR	<i>base</i>	CM frame, Q relative
SR	<i>base</i>	CM stack, S relative
GR	<i>base</i>	Group window
UR	<i>base</i> [<i>win_number</i>]	User window
VR	<i>base</i> [<i>win_number</i>]	Virtual window
ZR	<i>base</i>	Real memory window
LR	<i>base</i>	Ldev window

wS

Window shift. Shifts a window to the left or right. This command is defined for text windows (TX).

TXS	[<i>amount</i>] [<i>win_number</i>]
-----	---

wW

Defines (enables) new windows.

VW	<i>virtaddr</i>	[<i>name</i>]	Virtual window
ZW	<i>realaddr</i>		Real Memory
LW	<i>Ldev.off</i>		LDEV (Secondary Storage) window
TXW	<i>filename</i>		Text window
UWm			User window (see UWm command)

System Debug Function Specifications

This section presents short descriptions of the standard functions defined in System Debug. All functions are callable from both DAT and Debug.

func abstolog

Converts an CM absolute code address (ACPTR) to a CM logical code (LCPTR) address.

```
abstolog (cmabsaddr)
```

Formal Declaration

```
abstolog:lcptr (cmabsaddr:acptr)
```

func asc

Evaluates an expression and converts the result to an ASCII string.

```
asc (value [formatspec])
```

Formal Declaration

```
asc:str (value:any [formatspec:str = ''])
```

func ascc

Coerces an expression into a string value.

```
ascc (value)
```

Formal Declaration

```
ascc:str (value:any)
```

func bin

Converts a string expression to return a binary value.

```
bin (stexp)
```

Formal Declaration

```
bin:any (stexp:str)
```

func bitd

Bit deposit. Deposits a value into a specified range of bits.

```
bitd (value position length target)
```

Formal Declaration

```
bitd:any (value:any position:s16 length:u16 target:any)
```

func bitx

Bit extract. Extracts a range of bits from an expression.

```
bitx (source position length)
```

Formal Declaration

```
bitx:any (source:any position:s16 length:u16)
```

func bool

Coerces an expression into a Boolean value.

```
bool (value)
```

Formal Declaration

```
bool:bool (value:any)
```

func bound

Checks for an existing definition of an operand and returns its definition type.

```
bound (operand)
```

Formal Declaration

```
bound:str (operand:str)
```

func btow

Byte to word. Converts a CM DB-relative byte address to a CM DB-relative word address.

```
btow (byteaddress [splitstack])
```

Formal Declaration

```
btow:I16 (byteaddress:I16 [splitstack:bool=FALSE])
```

func cisetvar

Sets a new value for the specified CI (MPE/iX Command Interpreter) variable.

```
cisetvar (civarnam newvalue)
```

Formal Declaration

```
cisetvar:bool (civarnam:str newvalue:any)
```

func civar

Returns the current value of a CI (MPE/iX Command Interpreter) variable.

```
civar (civarnam [stropt])
```

Formal Declaration

```
civar:any (civaname:str [stropt:str="NOEV"])
```

func cmaddr

Converts a CM procedure name (or primary/secondary entry point) to a CM logical code address.

```
cmaddr (procname [lib])
```

Formal Declaration

```
cmaddr:lcptr (procname:str [lib:str=''])
```

func cmbpaddr

Returns the address corresponding to the indicated CM breakpoint index.

```
cmbpaddr (bpindex [pin])
```

Formal Declaration

```
cmbpaddr:lcptr (bpindex:u16 [pin:s16=0])
```

func cmbpindex

Returns the CM breakpoint index associated with the indicated CM code address.

```
cmbpindex (cmaddr [pin])
```

This function accepts the address (either logical or absolute) of an existing CM breakpoint and returns the logical index number associated with that breakpoint. The default action is to look for breakpoints set by the current PIN. Breakpoint indices for other PINs (including the global PIN) may be retrieved by utilizing the optional *pin* parameter.

Formal Declaration

```
cmbpindex:u16 (cmaddr:cptr [pin:s16=0])
```

func cmbpinstr

Returns the original CM instruction at a specified CM code address where a CM breakpoint has been set.

```
cmbpinstr (cmaddr [pin])
```

Formal Declaration

```
cmbpinstr:s16 (cmaddr:cptr [pin:s16=0])
```

func cmentry

Returns the CM (primary) entry point address of the CM procedure containing the specified CM logical code address.

```
cmentry (cmlogaddr)
```

Formal Declaration

```
cmentry:lcptr (cmlogaddr:lcptr)
```

func cmg

Returns the virtual address (SPTR) of a process's CMGLOBALS record.

```
cmg (pin)
```

Formal Declaration

```
cmg:sptr (pin:u16)
```

func cmnode

Returns the address of the closest CM node point corresponding to the specified CM logical code address.

```
cmnode (cmlogaddr [node])
```

Formal Declaration

```
cmnode:lcptr (cmlogaddr:lcptr [node:str="PREV"])
```

func cmproc

Returns the CM procedure name and offset corresponding to a CM logical code address.

```
cmproc (cmlogaddr)
```

Formal Declaration

```
cmproc:str (cmlogaddr:lcptr)
```

func cmproclen

Returns the length of the CM procedure which contains the specified CM logical code address.

```
cmproclen (cmlogaddr)
```

Formal Declaration

```
cmproclen:u16 (cmlogaddr:lcptr)
```

func cmseg

Returns the CM segment name for the specified CM logical code address.

```
cmseg (cmlogaddr)
```

Formal Declaration

```
cmseg:str (cmlogaddr:lcptr)
```

func cmstackbase

Returns the starting virtual address of a process's compatibility mode stack.

```
cmstackbase (pin)
```

Formal Declaration

```
cmstackbase:lptr (pin:u16)
```

func cmstackdst

Returns the DST number for a process's compatibility mode stack.

```
cmstackdst (pin)
```

Formal Declaration

```
cmstackdst:u16 (pin:u16)
```

func cmstacklimit

Returns the virtual address for the limit of a process's compatibility mode stack.

```
cmstacklimit (pin)
```

Formal Declaration

```
cmstacklimit:lptr (pin:u16)
```

func cmstart

Returns the starting point of the procedure containing the indicated CM logical code address.

```
cmstart (cmlogaddr)
```

Formal Declaration

```
cmstart:lpctr (cmlogaddr:lpctr)
```

func cmtonmnode

Returns the address of the closest NM node point corresponding to the specified CM logical code address.

```
cmtonmnode (cmlogaddr [node])
```

Formal Declaration

```
cmtonmnode:trans (cmlogaddr:lpctr [node:str=PREV])
```

func cmva

Returns the virtual address of a specified CM code address.

```
cmva (cmaddr [pin])
```

Formal Declaration

```
cmva:lpctr (cmaddr:cptr [pin:u16 = 0])
```

func cst

Coerces an expression into a CST absolute code pointer (ACPTR).

```
cst (value)
```

Formal Declaration

```
cst:cst (value:any)
```

func cstx

Coerces an expression into a CSTX absolute code pointer (ACPTR).

```
cstx (value)
```

Formal Declaration

```
cstx:cstx (value:any)
```

func dstva

Converts a CM data segment address to a virtual address.

```
dstva (dstoff)
```

Formal Declaration

```
dstva:lptr (dstoff:lptr)
```

func errmsg

Returns an error message string, based on error number and an optional subsystem number.

```
errmsg (errnum [subsys])
```

Formal Declaration

```
errmsg:str (errnum:s16 [subsys:u16=$a9])
```

func grp

Coerces an expression into a GRP logical code pointer (LCPTR).

```
grp (value)
```

Formal Declaration

```
grp:grp (value:any)
```

func hash

Hashes a virtual address into a hash table (real) offset.

```
hash (virtaddr)
```

Formal Declaration

```
hash:s32 (virtaddr:ptr)
```

func lgrp

Coerces an expression into a LGRP logical code pointer (LCPTR).

```
lgrp (value)
```

Formal Declaration

```
lgrp:lgrp (value:any)
```

func logtoabs

Logical to absolute. Converts a CM logical code address (LCPTR) into a CM absolute code address (ACPTR).

```
logtoabs (cmlogaddr)
```

Formal Declaration

```
logtoabs:acptr (cmlogaddr:lcptr)
```

func lptr

Coerces an expression into a long pointer.

```
lptr (value)
```

Formal Declaration

```
lptr:lptr (value:any)
```

func lpub

Coerces an expression into a LPUB logical code pointer (LCPTR).

```
lpub (value)
```

Formal Declaration

```
lpub:lpub (value:any)
```

func ltolog

Long to logical. Converts a long pointer into a NM logical code address (LCPTR).

```
ltolog (longptr)
```

Formal Declaration

```
ltolog:lcptr (longptr:lptr)
```

func ltos

Long to short. Converts a virtual address to a short pointer.

```
ltos (virtaddr)
```

Formal Declaration

```
ltos:sptr (virtaddr:ptr)
```

func macbody

Returns a string that is the macro body for the specified macro name.

```
macbody (macroname)
```

Formal Declaration

```
macbody:str (macroname:str)
```

func mapindex

Returns the map index number of the specified file name which has been previously mapped into virtual space with the MAP command.

```
mapindex (filename)
```

Formal Declaration

```
pindex:u16 (filename:str)
```

func mapsize

Returns the size in bytes of the specified mapped file.

```
mapsize (filename)
```

Formal Declaration

```
mapsize:u32 (filename:str)
```

func mapva

Returns the virtual address of the specified mapped file.

```
mapva (filename)
```

Formal Declaration

```
mapva:lptr (filename:str)
```

func nmaddr

Returns the virtual address of the specified NM procedure/data path.

```
nmaddr (path [lookupid])
```

Formal Declaration

```
nmaddr:long (path:str [lookupid:str="PROCEDURE"])
```

func nmbpaddr

Returns the address corresponding to the indicated NM breakpoint index.

```
%nmbpaddr (bpindex [pin])
```

Formal Declaration

```
nmbpaddr:lptr (bpindex:u32 [pin:s16=0])
```

func nmbpindex

Returns the NM breakpoint index for the NM breakpoint that has been set at the specified NM code address.

```
mbpindex (virtaddr [pin])
```

Formal Declaration

```
nmbpindex:u32 (virtaddr:ptr [pin:s16=0])
```

func nmbpinstr

Returns the original NM instruction at a specified NM code address where a NM breakpoint has been set.

```
nmbpinstr (virtaddr [pin])
```

Formal Declaration

```
nmbpinstr:s32 (virtaddr:ptr [pin:s16=0])
```

func nmcall

Dynamically calls a procedure/function passing up to four parameters.

```
nmcall (path) [parm1] [parm2] [parm3] [parm4]
```

Formal Declaration

```
nmcall:s32 (path:str [parm1:sptr=0][parm2:sptr=0]  
[parm3:sptr=0] [parm4:sptr=0])
```

func nmentry

Returns the entry point of the NM procedure containing the indicated address.

```
nmentry (virtaddr)
```

Formal Declaration

```
nmentry:lptr (virtaddr:ptr)
```

func nmfile

Returns the file name corresponding to the indicated NM (code) address.

```
nmfile (virtaddr [length])
```

Formal Declaration

```
nmfile:str (virtaddr:ptr [length:u16=$20])
```

func nmmod

Returns the NM module name corresponding to the indicated address.

```
nmmod (virtaddr [length])
```

Formal Declaration

```
nmmod:str (virtaddr:ptr [length:u16=$20])
```

func nmnode

Returns the NM logical code address (TRANS) of the closest NM node point corresponding to the specified NM address.

```
nmnode (virtaddr [node])
```

Formal Declaration

```
nmnode:trans (virtaddr:ptr [node:str="PREV"])
```

func nmpath

Returns the full NM code path name corresponding to the indicated address.

```
nmpath (virtaddr [length])
```

Formal Declaration

```
nmpath:str (virtaddr:ptr [length:u16=$50])
```

func nmproc

Returns the NM procedure name and offset corresponding to the specified virtual address.

```
nmproc (virtaddr [length])
```

Formal Declaration

```
nmproc:str (virtaddr:ptr [length:u16=$40])
```

func nmstackbase

Returns the virtual address of the start of the process's NM stack.

```
nmstackbase (pin)
```

Formal Declaration

```
nmstackbase:lptr (pin:u16)
```

func nmstacklimit

Returns the virtual address of the limit of a process's NM stack.

```
nmstacklimit (pin)
```

Formal Declaration

```
nmstacklimit:lptr (pin:u16)
```

func nmtocmnode

Returns the CM logical code address of the closest CM node point corresponding to the specified NM address.

```
nmtocmnode (virtaddr [node])
```

Formal Declaration

```
nmtocmnode:lcptr (virtaddr:lptr [node:str="PREV"])
```

func off

Returns the offset portion of a virtual address.

```
off (virtaddr)
```

Formal Declaration

```
off:u32 (virtaddr:ptr)
```

func pcb

Returns the virtual address (SPTR) of a process's PCB (process control block).

```
pcb (pin)
```

Formal Declaration

```
pcb:sptr (pin:u16)
```

func pcbx

Returns the virtual address (SPTR) of a process's PCBX (process control block extension).

```
pcbx (pin)
```

Formal Declaration

```
pcbx:sptr (pin:u16)
```

func phystolog

Converts a CM physical segment number and mapping bit to a CM logical code address.

```
phystolog (physsegnum [mappingbit])
```

Formal Declaration

```
phystolog:lcptr (physsegnum:u16 [mappingbit:bool=FALSE])
```

func pib

Returns the virtual address (SPTR) of a process's process information block (PIB).

```
pib (pin)
```

Formal Declaration

```
pib:sptr (pin:u16)
```

func pibx

Returns the virtual address (SPTR) of a process's process information block extension (PIBX).

```
pibx: (pin)
```

Formal Declaration

```
pibx:sptr (pin:u16)
```

func prog

Coerce an expression into a PROG logical code pointer (LCPTR).

```
prog (value)
```

Formal Declaration

```
prog:prog (value:any)
```

func pstate

Returns the process state, for the specified PIN, as a string.

```
pstate (pin)
```

Formal Declaration

```
pstate:str (pin:u16)
```

func pub

Coerces an expression into a PUB logical code pointer (LCPTR).

```
pub (value)
```

Formal Declaration

```
pub:pub (value:any)
```

func rtov

Real to virtual. Converts a real address to a virtual address.

```
rtov (realaddr)
```

Formal Declaration

```
rtov:lpstr (realaddr:u32)
```

func s16

Coerces an expression into a signed 16-bit value.

```
s16 (value)
```

Formal Declaration

```
s16:s16 (value:any)
```

func s32

Coerces an expression into a signed 32-bit value.

```
s32 (value)
```

Formal Declaration

```
s32:s32 (value:any)
```

func s64

Coerces an expression into a signed 64-bit value.

```
s64 (value)
```

Formal Declaration

```
s64:s64 (value:any)
```

func sid

Returns the space ID (SID) portion from a virtual address.

```
sid (virtaddr)
```

Formal Declaration

```
sid:u32 (virtaddr:ptr)
```

func sptr

Coerces an expression into a short pointer.

```
sptr (value)
```

Formal Declaration

```
sptr:sptr (value:any)
```

func stol

Short to long. Converts a virtual address to a long pointer.

```
stol (virtaddr)
```

Formal Declaration

```
stol:lptr (virtaddr:ptr)
```

func stolog

Short to logical. Converts a NM short pointer (SPTR) to a NM logical code address (LCPTR).

```
stolog (shortptr [logsel] [username])
```

Formal Declaration

```
stolog:lcptr (shortptr:sptr [logsel:str="PROG"] [username:str])
```

func str

Returns a substring of a source string.

```
str (source position length)
```

Formal Declaration

```
str:str (source:str position:u16 length:u16)
```

func strapp

String append. Returns the result of concatenating two strings.

```
strapp (source tail)
```

Formal Declaration

```
strapp:str (source:str tail:str)
```

func **strdel**

String delete. Returns a string with a substring deleted from the source string.

```
strdel (source position length)
```

Formal Declaration

```
strdel:str (source:str position:u16 length:u16)
```

func **strdown**

String downshift. Returns a string that is the result of downshifting all alphabetic characters in the source string.

```
strdown (source)
```

Formal Declaration

```
strdown:str (source:str)
```

func **strextact**

String extract. Returns a string (extracted) from the specified virtual address.

```
strextact (virtaddr [length])
```

Formal Declaration

```
strextact:str (virtaddr:ptr [length:u16=$4])
```

func **strinput**

Prompts on the input device for user input and returns the user input line as a string.

```
strinput (prompt)
```

Formal Declaration

```
strinput:str (prompt:str)
```

func **strins**

String insert. Returns a string after inserting another string into the source string.

```
strins (insert source position)
```

Formal Declaration

```
strins:str (insert:str source:str position:u16)
```

func **strlen**

String length. Returns the current size of a string.

```
strlen (source)
```

Formal Declaration

```
strlen:u32 (source:str)
```

func strltrim

String left trim. Deletes leading blanks from the source string.

```
strltrim (source)
```

Formal Declaration

```
strltrim:str (source:str)
```

func strmax

String maximum. Returns the (constant) maximum size of a string.

```
strmax (source)
```

Formal Declaration

```
strmax:u32 (source:str)
```

func strpos

String position. Returns the index of the first occurrence of one string in another.

```
strpos (source searchstring [position])
```

Formal Declaration

```
strpos:u32 (source:str searchstring:str [position:u32=1])
```

func strrpt

String repeat. Returns a string composed of repeated occurrences of a source string.

```
strrpt (source count)
```

Formal Declaration

```
strrpt:str (source:str count:u32)
```

func strrtrim

String right trim. Deletes trailing blanks from the source string.

```
strrtrim (source)
```

Formal Declaration

```
strrtrim:str (source:str)
```

func strup

String upshift. Returns a string which is the result of upshifting all alphabetic characters in the source string.

```
strup (source)
```

Formal Declaration

```
strup:str (source:str)
```

func **strwrite**

Returns a string which is the result of formatting one or more expressions in a manner equivalent to that of the W (WRITE) command.

```
strwrite (valuelist)
```

Formal Declaration

```
strwrite:str (valuelist:str)
```

func **symaddr**

Returns the bit- or byte-relative offset of a component specified through the path specification, relative to the outer structure.

```
symaddr (path [units])
```

Formal Declaration

```
symaddr:u32 (path:str [units:u16=8])
```

func **symconst**

Returns the value of a declared constant.

```
symconst (path)
```

Formal Declaration

```
symconst:any (path:str)
```

func **syminset**

Returns a Boolean value of TRUE if the set member specified by the member parameter is in the set specified by the virtual address and the path specification.

```
syminset (virtaddr path member)
```

Formal Declaration

```
syminset:bool (virtaddr:ptr path:str member:str)
```

func **symlen**

Returns the length of a data structure in bits or bytes.

```
symlen (path [units])
```

Formal Declaration

```
symlen:u32 (path:str [units:u32=$8])
```

func **symtype**

Returns the type of a component described by the path specification.

```
symtype (path)
```

Formal Declaration

```
symtype:int (path:str)
```

func symval

Returns the value of a simple data type specified by a virtual address and a path.

```
symval (virtaddr path)
```

Formal Declaration

```
symval:any (virtaddr:ptr path:str)
```

func sys

Coerces an expression into a SYS logical code pointer (LCPTR).

```
sys (value)
```

Formal Declaration

```
sys:sys (value:any)
```

func tcb

Returns the real address of a process's TCB (task control block).

```
tcb (pin)
```

Formal Declaration

```
tcb:u32 (pin:u16)
```

func trans

Coerces an expression into a TRANS logical code pointer (LCPTR).

```
trans (value)
```

Formal Declaration

```
trans:trans (value:any)
```

func typeof

Returns the type of an evaluated expression as a string.

```
typeof (expr)
```

Formal Declaration

```
typeof:str (expr:any)
```

func u16

Coerces an expression into an unsigned 16-bit value.

```
u16 (value)
```

Formal Declaration

```
u16:u16 (value:any)
```

func u32

Coerces an expression into an unsigned 32-bit value.

```
u32 (value)
```

Formal Declaration

```
u32:u32 (value:any)
```

func user

Coerces an expression into a USER library logical code pointer (LCPTR).

```
user ([library] value)
```

Formal Declaration

```
user:user ([library:str='' ] value:any)
```

func vainfo

Returns selected information for the specified virtual address.

```
vainfo (virtaddr selector)
```

Formal Declaration

```
vainfo:any (virtaddr:ptr selector:str)
```

func vtor

Virtual to real. Converts a virtual address to a real address.

```
vtor (virtaddr)
```

Formal Declaration

```
vtor:u32 (virtaddr:ptr)
```

func vtos

Virtual to secondary. Converts a virtual address to a secondary storage address.

```
vtos (virtaddr)
```

Formal Declaration

```
vtos:lptr (virtaddr:ptr)
```

System Debug Environment Variables

The following tables provide short descriptions of all System Debug environment variables, arranged by their logical groups. The information is organized as follows:

Group Name Access Rights Variable Name Return Type

Access rights abbreviations are listed below. PM indicates that privileged mode (PM) capability is required.

r Read access

System Debug
Debugging your system

R	PM read access
w	Write access
W	PM write access
d	Display access (DR command)
D	PM display access (DR command)
m	Modify access (MR command)
M	PM modify access (MR command)

const - constants

const	r	FALSE	: BOOL
const	r	TRUE	: BOOL

cmd - command related

cmd	rw	AUTOIGNORE	: BOOL
cmd	rw	AUTOREPEAT	: BOOL
cmd	rw	CMDLINESUBS	: BOOL
cmd	rw	CMDNUM	: U32
cmd	rw	ECHO_CMDS	: BOOL
cmd	rw	ECHO_SUBS	: BOOL
cmd	rw	ECHO_USE	: BOOL
cmd	rw	ERROR	: S32
cmd	r	MACRO_DEPTH	: U16
cmd	rw	MULTI_LINE_ERRS	: U16
cmd	rw	NONLOCALVARS	: BOOL
cmd	rw	TRACE_FUNC	: U16

io - input/output

io	rw	CM_INBASE	: STR
io	rw	CM_OUTBASE	: STR
io	r	COLUMN	: U16
io	rW	CONSOLE_IO	: BOOL (Debug only)
io	rw	FILL	: STR
io	rw	FILTER	: STR
io	rw	HEXUPSHIFT	: BOOL
io	rw	INBASE	: STR
io	rw	JUSTIFY	: STR
io	rw	LIST_INPUT	: BOOL
io	rw	LIST_PAGELEN	: U16
io	r	LIST_PAGENUM	: U16
io	rw	LIST_PAGING	: BOOL
io	rw	LIST_TITLE	: STR
io	rw	LIST_WIDTH	: U16
io	rw	NM_INBASE	: STR
io	rw	NM_OUTBASE	: STR
io	rw	OUTBASE	: STR
io	rw	PROMPT	: STR
io	rw	TERM_KEELOCK	: BOOL (Debug only)
io	rW	TERM_LDEV	: U16 (Debug only)
io	rw	TERM_LOCKING	: BOOL (Debug only)
io	rw	TERM_LOUD	: BOOL
io	rw	TERM_PAGING	: BOOL
io	rw	TERM_WIDTH	: U16

misc - miscellaneous

misc	rW	CCODE	: STR (Debug only)
misc	rW	CSTBASE	: LPTR
misc	r d	CPU	: U16
misc	r	DATE	: STR
misc	r	DISP	: BOOL
misc	rW	DSTBASE	: LPTR
misc	r	ENTRY_MODE	: STR

```

misc    rW    ESCAPECODE      : U32    (Debug only)
misc    r     EXEC_MODE       : STR
misc    r     ICSNEST        : U16
misc    r     ICSVA          : LPTR
misc    r     LASTPIN        : U16
misc    rw    LOOKUP_ID      : STR
misc    r     MODE           : STR
misc    r d   MONARCHCPU     : u16
misc    rw    MPEXL_TABLE-VA : LPTR
misc    r     PIN            : U16
misc    rW    PRIV_USER      : BOOL
misc    r     PROGNAME       : STR
misc    rw    PSTMT          : U16
misc    rw    QUIET_MODIFY   : BOOL
misc    r     SYSVERSION     : STR
misc    r     TIME           : STR
misc    r     VERSION        : STR

```

win - window

```

win     rw    CHANGES       : STR
win     rw    CMPW          : LCPTR
win     r     LW            : LPTR
win     rw    MARKERS       : STR
win     r     NMPW         : LCPTR
win     r     PW           : LCPTR
win     r     PWO          : SPTR
win     r     PWS          : U32
win     r     SHOW_CCTL    : BOOL
win     r     VW           : LPTR
win     r     VWO          : SPTR
win     r     VWS          : U32
win     rw    WIN_LENGTH    : U32
win     rw    WIN_WIDTH     : U32
win     r     ZW           : U32

```

limits - limits for macros and variables

```

limits  rw    MACROS         : U16
limits  r     MACROS_LIMIT  : U16
limits  rw    VARS          : U16
limits  r     VARS_LIMIT   : U16
limits  rw    VARS_LOC      : U16
limits  r     VARS_TABLE   : U16

```

cmreg - compatibility mode regs

```

cmreg   r dm  CIR           : S16
cmreg   r dm  CMPC         : LCPTR
cmreg   r dm  DB           : S16
cmreg   r dm  DBDST        : S16
cmreg   r dm  DL           : S16
cmreg   r d   MAPDST       : S16
cmreg   r d   MAPFLAG      : S16
cmreg   r dm  Q            : S16
cmreg   r dm  S            : S16
cmreg   r dm  SDST        : S16
cmreg   r dm  STATUS       : S16
cmreg   r dm  X            : S16

```

nmreg - native mode regs

```

nmreg   r dm  ARG0 - ARG3  : U32
nmreg   r dm  CCR          : U16
nmreg   r dm  CR0         : U32
nmreg   r dm  CR8 - CR31  : U32
nmreg   r dm  DP          : U32
nmreg   r dm  EIEM        : U32
nmreg   r dm  EIRR        : U32
nmreg   r dm  IIR        : U32
nmreg   r dm  IOR         : U32
nmreg   r dm  IPSW        : U32
nmreg   r dm  ISR         : U32
nmreg   r dm  ITMR        : U32

```

System Debug

Debugging your system

```
nmreg  r dM  IVA                : U32
nmreg  r dM  PC                  : LPTR
nmreg  r dM  PCOB                : U32
nmreg  r dM  PCOF                : U32
nmreg  r dM  PCQB                : LPTR
nmreg  r dM  PCQF                : LPTR
nmreg  r dM  PCSB                : U32
nmreg  r dM  PCSF                : U32
nmreg  r dM  PID1 - PID4        : U16
nmreg  r dM  PRIV                : BOOL
nmreg  r d   PSP                 : U32
nmreg  r dM  PSW                 : U32
nmreg  r d   R0                  : U32
nmreg  r dM  R1 - R31           : U32
nmreg  r dM  RCTR                : U32
nmreg  r dM  RET0               : U32
nmreg  r dM  RET1               : U32
nmreg  r d   RP                  : U32
nmreg  r dM  SAR                 : U16
nmreg  r dM  SL                  : U32
nmreg  r dM  SP                  : U32
nmreg  r dM  SR0 - SR7         : U32
nmreg  r dM  TR0 - TR7         : U32
```

fpreg - floating point regs

```
fpreg  r dM  FPSTATUS           : U32
fpreg  r dM  FP0 - FP15         : LPTR   (until S64 is supported)
fpreg  r dM  FPE0 - FPE7       : U32
```

system - system wide debug

```
system rW   CONSOLE_DEBUG       : BOOL   (Debug only)
system rW   JOB_DEBUG            : BOOL   (Debug only)
system rW   DYING_DEBUG          : BOOL   (Debug only)
```

state - process state

The *state* variables consist of all NMREG, CMREG, and FPREG variables.

7 File System

System Defined Files

MPE/iX reserves certain file designators for system defined files. System defined files are reserved words that refer to a specific type of system file.

\$STDIN	refers to the device that you used to initiate your current session or job. The device is normally a terminal for a session and spoolfile for a job. Data entries in this file should not have a colon in column 1. (A colon in column 1 indicates the end-of-data). Use the :EOD command to delimit data.
\$STDINX	is the same as \$STDIN, except that a colon in the first column does not indicate the end of data. Thus \$STDINX may contain commands as well as data. Interactive programs and subsystems often use \$STDINX to reference the terminal as an input file. Use :EOD or :EOF to indicate the end of data.
\$STDLIST	is the device designated as the session or job output device, the device MPE uses to respond to your commands. This device is normally a terminal for sessions and line printer for jobs.
\$NULL	is a file designator that is used to tell MPE to read from or write to a non-existent file as though the input-output operation were successful. This file is usually used to discard output.
\$NEWPASS	is a temporary disk file. MPE uses \$NEWPASS to store information during the execution of a program. When a program closes \$NEWPASS, the system automatically changes its name to \$OLDPASS.
\$OLDPASS	is a temporary disk file containing the contents of the last \$NEWPASS file closed. When a \$NEWPASS file is renamed \$OLDPASS, the system deletes the previous version of \$OLDPASS.

You can use \$NEWPASS and \$OLDPASS when compiling and preparing a program. MPE compilers write object code to \$NEWPASS during compilation. When compilation is complete, the compiler closes \$NEWPASS and the system renames the object code (USL) file \$OLDPASS. When you prepare the USL file (\$OLDPASS), the system stores prepared (executable) code in the \$NEWPASS file. When preparation is complete, the system closes \$NEWPASS and renames the executable code file \$OLDPASS. Use the SAVE command to save the program stored in \$OLDPASS to a permanent file.

Table 7-1 FFILEINFO File codes

Integer	Mnemonic	Description
0		Default (unreserved)
1024	USL	User subprogram library
1025	BASD	Basic data
1026	BASP	Basic program
1027	BASFP	Basic fast program
1028	RL	Compatibility mode relocatable library
1029	PROG	Compatibility mode program file
1030	NMPRG	Native mode program file
1031	SL	Segmented library
1032	NMSL	Native mode executable library
1033	NMRL	Native mode relocatable library
1035	VFORM	VPLUS forms file
1036	VFAST	VPLUS fast forms file
1037	VREF	VPLUS reformat file
1040	XLSAV	Cross loader ASCII file (SAVE)
1041	XLBIN	Cross loader relocated binary file
1042	XLDSP	Cross loader ASCII file (DISPLAY)
1050	EDITQ	Edit quick file
1051	EDTCQ	Edit KEEPQ file (COBOL)
1052	EDTCT	Edit TEXT file (COBOL)
1054	TDPDT	TDP diary file
1055	TDPQM	TDP proof marked QMARKED
1056	TDPP	TDP proof marked non-COBOL file
1057	TDPCP	TDP proof marked COBOL file
1058	TDPQ	TDP work file
1059	TDPXQ	TDP work file (COBOL)
1060	RJEPN	RJE punch file
1070	QPROC	QUERY procedure file
1080	KSAMK	KSAM key file

Integer	Mnemonic	Description
1083	GRAPH	GRAPH specification file
1084	SD	Self-describing file
1090	LOG	User logging log file
1100	WDOC	HPWORD document
1101	WDICT	HPWORD hyphenation dictionary
1102	WCONF	HPWORD configuration file
1103	W2601	HPWORD attended printer environment
1110	PCELL	IFS 3000/XL character cell file
1111	PFORM	IFS 3000/XL form file
1112	PENV	IFS 3000/XL environment file
1113	PCCMP	IFS 3000/XL compiled character cell file
1114	RASTR	Graphics image in RASTR format
1130	OPTLF	OPT/3000 log file
1131	TEPES	TEPE/3000 script file
1132	TEPEL	TEPE/3000 log file
1133	SAMPL	APS/3000 log file
1139	MPEDL	MPEDCP/DRP log file
1140	TSR	HPToolset root file
1141	TSD	HPToolset data file
1145	DRAW	Drawing file for HPDRAW
1146	FIG	Figure file for HPDRAW
1147	FONT	Reserved
1148	COLOR	Reserved
1149	D48	Reserved
1152	SLATE	Compressed SLATE file
1153	SLATW	Expanded SLATE work file
1156	DSTOR	RAPID/3000 DICTDBU utility store file
1157	TCODE	Code file for Transact/XL compiler
1158	RCODE	Code file for Report/3000 compiler
1159	ICODE	Code file for Inform/3000 compiler

Integer	Mnemonic	Description
1166	MDIST	HPDesk distribution list
1167	MTEXT	HPDesk text
1168	MARPA	ARPA messages file
1169	MARPD	ARPA distribution list
1170	MCMND	HPDesk abbreviated commands file
1171	MFRTM	HPDesk diary free time list
1172	None	Reserved
1173	MEFT	HPDesk external file transfer messages file
1174	MCRPT	HPDesk encrypted item
1175	MSERL	HPDesk serialized (composite) item
1176	VCSF	Reserved
1177	TTYPE	Terminal type file
1178	TVFC	Terminal vertical format control file
1192	NCONF	Network configuration file
1193	NTRAC	Network trace file
1194	NLOG	Network log file
1195	MIDAS	Reserved
1211	ANODE	Reserved
1212	INODE	Reserved
1213	INVRT	Reserved
1214	EXCEP	Reserved
1215	TAXON	Reserved
1216	QUERF	Reserved
1217	DOCDR	Reserved
1226	VC	VC file
1227	DIF	DIF file
1228	LANGD	Language definition file
1229	CHARD	Character set definition file
1230	MGCAT	Formatted application file

File System
System Defined Files

Integer	Mnemonic	Description
1236	BMAP	Base map specification file
1242	BDATA	BASIC data file
1243	BFORM	BASIC field order file for VPLUS
1244	BSAVE	BASIC saved program file
1245	BCNFG	Configuration file for default option BASIC program
1258	PFSTA	Pathflow static file
1259	PFDYN	Pathflow dynamic file
1270	RFDCA	Revisable form DCA data stream
1271	FFDCA	Final form DCA data stream
1272	DIU	Document interchange unit file
1273	PDOC	HPWORD/150 document
1401	CWPTX	Reserved
1421	MAP	HPMAP/3000 map specification file
1422	GAL	Reserved
1425	TTX	Reserved
1461	NMOBJ	Native mode object file
1462	PASLB	Pascal/iX source library

Table 7-2 Carriage Control Directives

Octal Code (ASCII)	Description of Carriage Action
%2 - %37 (" ")	Single space (with or without automatic page eject)
%40 - %52 (" ")	Single space (with or without automatic page eject)
%53 ("+")	No space, return (next printing at column 1), cannot be used more than once on the HP 2608A/S without losing data
%54 (" ")	Single space (with or without automatic page eject)
%55 ("-")	Triple space (with or without automatic page eject)
%56 - %57 (" ")	Single space (with or without automatic page eject)
%60 ("0")	Double space (with or without automatic page eject)
%61 ("1 ")	<p>Conditional page eject (form feed) performed by the software; if the printer is not at top-of-form, a page eject is performed. Ignored if:</p> <p>Postspace mode The current request has a transfer count of 0 and the previous request was FOPEN, HPFOPEN, FCLOSE, or FWRITE specifying a carriage-control directive of %61.</p> <p>Prespace mode Both the current request and the previous request have transfer counts of 0, and the current request and previous request are any combination of FOPEN, HPFOPEN, FCLOSE, or FWRITE specifying a carriage-control of %61.</p>
%62	Skip to one line before top of form (valid for HP 2608S and 2563A printers only)
%63	A conditional page eject form feed is performed by the printer; not at top-of-form, a page eject is performed (valid for HP 2608S and 2563A printers only)
%62 - %77 (" ")	Single space (with or without automatic page eject; for terminals)
%104 - %177 (" ")	Single space (with or without automatic page eject; for terminals)
%2nn	Space <i>nn</i> lines (no automatic page eject); <i>nn</i> is any octal number from 0 through 77
%300 - %313	Select VFC Channel 1 - 12 (HP 2613, 2617, 2618, 2619)
%300 - %317	Select VFC Channel 1 - 16 (HP 2608A/S)
%300	Skip to top of form (page eject)
%301	Skip to bottom of form
%302	Single spacing with automatic page eject
%303	Skip to next odd line with automatic page eject
%304	Skip to next third line with automatic page eject

Octal Code (ASCII)	Description of Carriage Action
%305	Skip to next 1/2 page
%306	Skip to next 1/4 page
%307	Skip to next 1/6 page
%310	Skip to bottom of form
%311	User option (HP 2613/17/18/19), skip to one line before bottom of form (HP 2608A/S)
%312	User option (HP 2613/17/18/19), skip to one line before top of form (HP 2608A/S)
%313	User option (HP 2613/17/18/19), skip to top of form (HP 2608A)
%314	Skip to next seventh line with automatic page eject
%315	Skip to next sixth line with automatic page eject
%316	Skip to next fifth line with automatic page eject
%317	Skip to next fourth line with automatic page eject
%310 - %317	(HP 2607)
%314 - %317	(HP 2613/17/18/19)
%320	No space, no return (next printing physically follows this)
%321-%377 (" ")	Single space (with or without automatic page eject)
%400 or %100	Sets postspace movement option (prints first, then spaces). If previous option was prespace movement, the driver outputs a line with a skip to VFC Channel 3 (automatic page eject in effect) or a one line advance (equivalent to an octal code of %201 without automatic page eject) to clear the buffer
%401 or %101	Sets prespace movement option (spaces first, then prints)
%402 or %102	Sets single-space option, with automatic page eject (60 lines per page)
%403 or %103	Sets single-space option, without automatic page eject (66 lines per page)

NOTE If octal codes %55 and %60 are selected with automatic page eject in effect (by default or following an octal code of %102 or %402), the resulting skip is to a location absolute to the page. A code of %60 is replaced by %303, and a code of %55 is replaced by %304. Therefore, the resulting skip can be less than two or three lines, respectively.

If automatic page eject is not in effect, a true double or triple space results, but the perforation between pages is not automatically skipped. For the HP 2608S and 2563A, if auto-eject and feature mode are in

effect, a code of %60 is replaced by two codes of %302, and a code of %55 is replaced by three codes of %302. The resulting skip is double or triple space with auto-eject, respectively.

Carriage Control Effect Summary

FOPEN OR :FILE	FWRITE Control Parameter		
	= 0	= 1	= Greater than 1
Carriage Control Foption or CCTL	Recsize = 133 Byte 1 0 record = 132 Data output contains 132 characters; the prefix byte is added and contains 0.	Recsize = 132 record = 132 Data output contains 132 characters; the carriage control character in the first byte is not printed if output is to a list device.	Recsize = 133 Byte 1 Con- record = 132 trol Data output contains 132 characters; the prefix character added is a carriage control character specified by the FWRITE control parameter.
Carriage Control Foption not specified or NOCCTL	132 record = 132 Data output contains 132 characters.	132 record = 132 Data output contains 132 characters.	132 record = 132 Data output contains 132 characters.

Effect on Data Output

LG200154_001

File Access and Security

Table 7-3 File Access and Security

Mode	User
R = Read	ANY = Any user
L = Lock (allows exclusive access to the file)	AC = Member of this account only
A = Append (implicitly specifies L also)	GU = Member of this group only
W = Write (implicitly specifies A and L also)	AL = Account librarian user only
X = Execute	GL = Group librarian user only
S = Save	CR = Creating user only

Default Security for Accounts, Groups, and Users

Table 7-4 **Security for Accounts, Groups and Users**

Type	Access Permitted
SYS account	(R,X:ANY;W,A,L:AC)
Accounts other than SYS	(R,X,W,A,L:AC)
PUB groups in any account	(R,X:ANY;A,W,L,S:AL,GU)
Groups other than PUB	(R,X,S,W,A,L:GU)
Users with no security specified	(R,X,W,A,L:ANY)

Net Default Access to Files

Table 7-5 Net Default Access to Files

Filereference	File	Access Permitted	Save Access to Group
Filename.PUB.SYS	Any file in Public (PUB) group of System (SYS) account.	(R, X: ANY; W: AL, GU)	AL, GU
Filename.grp.SYS	Any file in any group in SYS account.	(R, W, X: GU)	GU
Filename.PUB.acct	Any file in PUB group of any account.	(R, X: AC; W: AL, GU)	AL, GU
Filename.grp.acct	Any file in any group in any account.	(R, W, X: GU)	GU

Capability List

Table 7-6 **Capability List**

Capability	Mnemonic	Capability	Mnemonic
System manager	= SM	Use private volumes	= UV
Account manager	= AM	Create volumes	= CV
Account librarian	= AL	Use communication	
Group librarian	= GL	software	= CS
Diagnostician	= DI	Programmatic sessions	= PS
System supervisor	= OP	User logging	= LG
Network administrator	= NA	Process handling	= PH
Node manager	= NM	Extra data segments	= DS
Permanent files	= SF	Multiple RINs	= MR
Access of nonshareable		Privileged mode	= PM
I/O devices	= ND	Interactive access	= IA
		Batch access	= BA

Default Capabilities

Table 7-7 **Default Capabilities**

	Type	Capabilities
Accounts		AM, AL, GL, SF, ND, IA, BA
Groups		IA, BA
Users		SF, ND, IA, BA

FOPEN FOPTIONS

FOPEN FOPTIONS

Bits	(0:2)	(2:3)	(5:1)	(6:1)	(7:1)	(8:2)	(10:3)	(13:1)	(14:2)
Field	Reserved	File Type	Disallow :FILE	MPE Tape Labels	Carriage Control	Record Format	Default File Designator	ASCII BINARY	Domain
Meaning		00 0=STD 00 1=KSAM 01 0=RIO 10 0=CIR 11 0=MSG	0 = Allow :FILE 1 = No :FILE	0 = Non-Labeled Tape 1 = Labeled Tape	0 = NOCCTL 1 = CCTL	00 = Fixed 01 = Variable 10 = Undefined 11 = Spoolfile	000 = FILENAME 001 = \$STDLIST 010 = \$NEWPASS 011 = \$OLDPASS 100 = \$STDIN 101 = \$STDINX 110 = \$NULL	0 = BINARY 1 = ASCII	00 = New File 01 = Old Permanent File 10 = Old Temporary File 11 = Old Permanent or Temporary File

LG200154_002

NOTE: Double lines indicate octal digit boundaries.

FOPEN AOPTIONS

FOPEN AOPTIONS

Bits	(0:3)	(3:1)	(4:1)	(5:2)	(7:1)	(8:2)	(10:1)	(11:1)	(12:4)
Field	Reserved	File Copy Access	NOWAIT I/O	Multi-Access	Inhibit Buffering	Exclusive Access	Dynamic Locking	Multi-Record Access	Access Type
Meaning		0 = Access Native Mode 1 = Access as Standard Sequential	0 = NOWAIT 1 = Non-NOWAIT	00 = Non Multi-Access 01 = Only Intra-Job Multi-Access 10 = Inter-Job Multi-Access Allowed	0 = BUF 1 = NOBUF	00 = Default 01 = Exclusive 10 = Semi-Exclusive Access Read 11 = Share	0 = No FLOCK Allowed 1 = FLOCK Allowed	0 = No Multi-Record 1 = Multi-Record	000 = Read Only 001 = Write Only 010 = Write (Save) Only 011 = Append Only 100 = Read/Write 101 = Update 110 = Execute

LG200154_003

NOTE: Double lines indicate octal digit boundaries.

8 ASCII Character Set

ASCII Character Set

Table 8-1 **ASCII Character Set**

Hex.	Dec.	Octal Left	Octal Right	Char
00	0	000000	000000	NUL (null)
01	1	000400	000001	SOH (start of heading)
02	2	001000	000002	STX (start of text)
03	3	001400	000003	ETX (end of text)
04	4	002000	000004	EOT (end of transmission)
05	5	002400	000005	ENQ (enquiry)
06	6	003000	000006	ACK (acknowledge)
07	7	003400	000007	BEL (bell)
08	8	004000	000010	BS (backspace)
09	9	004400	000011	HT (horizontal tabulation)
0A	10	005000	000012	LF (line feed)
0B	11	005400	000013	VT (vertical tabulation)
0C	12	006000	000014	FF (form feed)
0D	13	006400	000015	CR (carriage return)
0E	14	007000	000016	SO (shift out)
0F	15	007400	000017	SI (shift in)
10	16	010000	000020	DLE (data link escape)
11	17	010400	000021	DC1 (device control 1, X-ON)
12	18	011000	000022	DC2 (device control 2)
13	19	011400	000023	DC3 (device control 3, X-OFF)
14	20	012000	000024	DC4 (device control 4)
15	21	012400	000025	NAK (negative acknowledge)
16	22	013000	000026	SYN (synchronous idle)
17	23	013400	000027	ETB (end of transmission block)
18	24	014000	000030	CAN (cancel)
19	25	014400	000031	EM (end of medium)
1A	26	015000	000032	SUB (substitute)

Hex.	Dec.	Octal Left	Octal Right	Char
1B	27	015400	000033	ESC (escape)
1C	28	016000	000034	FS (file separator)
1D	29	016400	000035	GS (group separator)
1E	30	017000	000036	RS (record separator)
1F	31	017400	000037	US (unit separator)
20	32	020000	000040	blank
21	33	020400	000041	!
22	34	021000	000042	"
23	35	021400	000043	#
24	36	022000	000044	\$
25	37	022400	000045	%
26	38	023000	000046	&
27	39	023400	000047	' (closing single quote)
28	40	024000	000050	(
29	41	024400	000051)
2A	42	025000	000052	*
2B	43	025400	000053	+
2C	44	026000	000054	, (comma)
2D	45	026400	000055	-
2E	46	027000	000056	. (period)
2F	47	027400	000057	/
30	48	030000	000060	0
31	49	030400	000061	1
32	50	031000	000062	2
33	51	031400	000063	3
34	52	032000	000064	4
35	53	032400	000065	5
36	54	033000	000066	6
37	55	033400	000067	7
38	56	034000	000070	8

ASCII Character Set
 ASCII Character Set

Hex.	Dec.	Octal Left	Octal Right	Char
39	57	034400	000071	9
3A	58	035000	000072	:(colon)
3B	59	035400	000073	;(semicolon)
3C	60	036000	000074	<
3D	61	036400	000075	=
3E	62	037000	000076	>
3F	63	037400	000077	?
40	64	040000	000100	@
41	65	040400	000101	A
42	66	041000	000102	B
43	67	041400	000103	C
44	68	042000	000104	D
45	69	042400	000105	E
46	70	043000	000106	F
47	71	043400	000107	G
48	72	044000	000110	H
49	73	044400	000111	I
4A	74	045000	000112	J
4B	75	045400	000113	K
4C	76	046000	000114	L
4D	77	046400	000115	M
4E	78	047000	000116	N
4F	79	047400	000117	O
50	80	050000	000120	P
51	81	050400	000121	Q
52	82	051000	000122	R
53	83	051400	000123	S
54	84	052000	000124	T
55	85	052400	000125	U
56	86	053000	000126	V

Hex.	Dec.	Octal Left	Octal Right	Char
57	87	053400	000127	W
58	88	054000	000130	X
59	89	054400	000131	Y
5A	90	055000	000132	Z
5B	91	055400	000133	[
5C	92	056000	000134	\
5D	93	056400	000135]
5E	94	057000	000136	^ (caret)
5F	95	057400	000137	_ (underscore)
60	96	060000	000140	` (opening single quote)
61	97	060400	000141	a
62	98	061000	000142	b
63	99	061400	000143	c
64	100	062000	000144	d
65	101	062400	000145	e
66	102	063000	000146	f
67	103	063400	000147	g
68	104	064000	000150	h
69	105	064400	000151	i
6A	106	065000	000152	j
6B	107	065400	000153	k
6C	108	066000	000154	l
6D	109	066400	000155	m
6E	110	067000	000156	n
6F	111	067400	000157	o
70	112	070000	000160	p
71	113	070400	000161	q
72	114	071000	000162	r
73	115	071400	000163	s
74	116	072000	000164	t

ASCII Character Set
ASCII Character Set

Hex.	Dec.	Octal Left	Octal Right	Char
75	117	072400	000165	u
76	118	073000	000166	v
77	119	073400	000167	w
78	120	074000	000170	x
79	121	074400	000171	y
7A	122	075000	000172	z
7B	123	075400	000173	{
7C	124	076000	000174	(vertical line)
7D	125	076400	000175	}
7E	126	077000	000176	~ (tilde)
7F	127	077400	000177	DEL delete